

FG

AD A 037963

6

COMPUTER PROGRAMS FOR SEISMOLOGY: SPECIAL APPLICATIONS TO THE HIGH-GAIN LONG-PERIOD SEISMIC NETWORK


By

DUNCAN M. CHESLEY and EDUARD BERG

MARCH 1976

Prepared for
AIR FORCE OFFICE OF SCIENTIFIC RESEARCH
under Contract AFOSR-74-2612
ARPA Order 1827

Distribution of this document is unlimited.
Reproduction in whole or in part is permitted
for any purpose of the United States Government.



FILE COPY

DDC

HAWAII INSTITUTE OF GEOPHYSICS
UNIVERSITY OF HAWAII



AIR FORCE OFFICE OF SCIENTIFIC RESEARCH (AFSC)
NOTICE OF TRANSMITTAL TO DDC
This technical report has been reviewed and is
approved for public release IAW AFR 190-12 (7b).
Distribution is unlimited.
A. D. BLOSE
Technical Information Officer

Unclassified

SECURITY CLASSIFICATION OF THIS PAGE (When Data Entered)

(18) REPORT DOCUMENTATION PAGE REPORT NUMBER AFOSR - TR - 77 - 0257		READ INSTRUCTIONS BEFORE COMPLETING FORM 9
<small>6. FILE (and Subtitle)</small> Computer Programs for Seismology: Special Applications to the High-Gain Long-Period Seismic Network.		<small>3. RECIPIENT'S CATALOG NUMBER</small> Interim <small>4. PERIOD OF REPORT & PERIOD COVERED</small> HIG-76-3 <small>5. PERFORMING ORG. REPORT NUMBER</small> HIG-76-3 <small>6. CONTRACT OR GRANT NUMBER(s)</small> AFOSR 74-2612
<small>7. AUTHOR(s)</small> DUNCAN M. CHESLEY AND EDUARD BERG		<small>10. PROGRAM ELEMENT, PROJECT, TASK AREA & WORK UNIT NUMBERS</small> 62701E 4F10 1827-21
<small>9. PERFORMING ORGANIZATION NAME AND ADDRESS</small> Hawaii Institute of Geophysics, Univ of Hawaii. Honolulu, Hawaii 96822		<small>12. REPORT DATE</small> Mar 1976
<small>11. CONTROLLING OFFICE NAME AND ADDRESS</small> ARPA/NMR 1400 Wilson Blvd. Arlington VA 22209		<small>13. NUMBER OF PAGES</small> -104-
<small>14. MONITORING AGENCY NAME & ADDRESS (if different from Controlling Office)</small> AFOSR/NP Bolling AFB, Bldg. #410 Wash DC 20332		<small>15. SECURITY CLASS. (of this report)</small> Unclassified
<small>16. DISTRIBUTION STATEMENT (of this Report)</small> Approved for public release: distribution unlimited.		
12) 76p.	15) AF-AFOSR-2612-74	
<small>17. DISTRIBUTION STATEMENT (of the abstract entered in Block 20, if different from Report)</small> ✓ARPA Order - 1827		
<small>18. SUPPLEMENTARY NOTES</small> TECH, OTHER		
<small>19. KEY WORDS (Continue on reverse side if necessary and identify by block number)</small> Computer Programs. HGLP stations, Filter Rotation Signal extraction, Amplitude determination, Ground motion Beam focusing.		
<small>20. ABSTRACT (Continue on reverse side if necessary and identify by block number)</small> <p>This report describes several IBM 370/158 computer programs that have been applied to long-period seismic data on digital tapes. Included are reading routines for tapes generated by the high-gain long-period (HGLP) stations, rotation of the horizontal components, low-, band-, and high-pass digital filters, correlation (or matched filtering), summation of correlations, beam focusing, and ground motion retrieval.</p> <p>Results of applications, described elsewhere or in preparation, include (cont'd)</p>		

20. ABSTRACT (cont'd.)

extraction and amplitude determination of Rayleigh waves with signal-to-noise ratios near 1 to 10, precision amplitude and phase calibration of entire seismic systems from transducer to final record, beam forming of matched filtered outputs from the randomly spaced HGLP station array, and separation of colocated multiple events with time spacing as short as 150 sec or separation of events widely spaced geographically but arriving nearly simultaneously at a given station.

White Section	<input checked="" type="checkbox"/>
Buff Section	<input type="checkbox"/>
RECORDED	<input type="checkbox"/>
SERIALIZED	<input type="checkbox"/>
DISTRIBUTION/AVAILABILITY CODES	
DATE	AVAIL. AND/OR SPECIAL
P	

HIG-76-3

COMPUTER PROGRAMS FOR SEISMOLOGY:
SPECIAL APPLICATIONS TO THE
HIGH-GAIN LONG-PERIOD SEISMIC NETWORK

By
Duncan M. Chesley and Eduard Berg

March 1976

Prepared for
Air Force Office of Scientific Research
under Contract AFOSR-74-2612
ARPA Order No. 1827



Approved by Director
George T. Woodland

Date: 22 March 1976

DISTRIBUTION STATEMENT A	
Approved for public release; Distribution Unlimited	

Abstract

This report describes several IBM 370/158 computer programs that have been applied to long-period seismic data on digital tapes. Included are reading routines for tapes generated by the high-gain long-period (HGLP) stations, rotation of the horizontal components, low-, band- and high-pass digital filters, correlation (or matched filtering), summation of correlations, beam focusing, and ground motion retrieval.

Results of applications, described elsewhere or in preparation, include extraction and amplitude determination of Rayleigh waves with signal-to-noise ratios near 1 to 10, precision amplitude and phase calibration of entire seismic systems from transducer to final record, beam forming of matched filtered outputs from the randomly spaced HGLP station array, and separation of colocated multiple events with time spacing as short as 150 sec or separation of events widely spaced geographically but arriving nearly simultaneously at a given station.

Table of Contents

	Page
ABSTRACT	iii
ACKNOWLEDGMENTS	vii
INTRODUCTION	1
SYSTEM STRUCTURE	4
REFERENCES	11
SUBROUTINES	12
AVENUL	15
BPFILT	17
COREAD	19
CORRL8	23
DOFILT	29
DSPYK	31
FASTO	35
FIND	37
FINDB	41
FLTADJ	43
HAMING	45
HDCONV	47
HD2SEC	49
HPFILT	51
INFILT	53
KREAD	55
LPFILT	57

	Page
MAXMIN	59
PLOTB	61
PLT1	65
PRPLT1	71
READ	73
ROTATE	79
SEC2HD	81
SETCC, SETNP, SETXYN	83
SHRINK	87
TABLE	89
WRTSUM	91
SAMPLE PROGRAMS AND JCL	92

Acknowledgments

The authors thank Andrew Lazarewicz and Karl Hinck for their assistance with the computer programming. Special gratitude is extended to Dr. G. H. Sutton for his continued interest and support and for many illuminating discussions.

This research was supported by the Advanced Research Project Agency of the Department of Defense and was monitored by the Air Force Office of Scientific Research under Contract AFOSR 74-2612.

Introduction

The system of programs and subroutines described here has evolved over a number of years of research using digital data tapes from High-Gain Long-Period Seismic stations in studies of seismic surface waves. A prototype was described by Pomeroy et al. (1969), and operational systems have been documented in detail in a Lamont-Doherty Geological Observatory report (1971). E. Berg, principal investigator on the project, set the goals, elaborated most of the mathematics, and checked and interpreted the results; D. Chesley performed almost all of the programming. The results presented here were accomplished through close daily interaction between programming and verification of the outputs. Since several Hawaii Institute of Geophysics (HIG) staff members contributed to the effort, the programmer's name for each subroutine has been listed under 'source' in the program descriptions.

Published applications of the programs to detection and amplitude determination of extremely weak Rayleigh waves (Berg, 1974, 1975) include examples of both the type of output obtainable from the programs, and the mathematics involved. An additional application is in obtaining the automated amplitude and phase response of a complete seismometer-recording system from step inputs to the calibration coil (or similar calibration devices), where high accuracy is achieved by summing into an operating system as many individual pulses as

desired (to eliminate the ever-present background noise) by the use of correlation and subsequent Fourier analysis. The only parameters required are the seismometer mass, the calibration coil constant (referred to the center of mass if appropriate) and current, and the precise onset time of one reference calibration current. This work (Berg and Chesley, in press) is especially applicable to large arrays and remote-control systems with complicated transmission interfaces to the recording site. Other applications to geophysical data come readily to mind, but will not be discussed here.

Most of the routines are written in FORTRAN and are meant for use on the IBM 370/158 computer. The programs accomplish all data handling, from reading the tape to plotting and tabulating the results of various manipulations.

The programmer intended that the programs and subroutines should interact with a minimum of input from the user. Thus a typical main program supplied by the user will consist of a few initialization statements followed by CALL statements that refer to the subroutines, where all of the analysis is performed. If a user wishes to extract information from his tapes using one of the subroutines listed in this report, he needs only to copy the appropriate sample program from the report; or he may generate his own program to access the subroutines according to his specific needs.

The reader is cautioned against modifying the subroutines. Their interaction is quite complex, and a seemingly innocuous

change in one routine could require extensive modifications in other subprograms.

Most of the programs are designed for analysis of seismic velocity output (A-channel) data; exceptions are FINDB and PLOTB. The A-channel format is 1 data point per second, 555 seconds per record, on 556-bit-per-inch magnetic tape, and the B channels are digitized at 1 data point per 5 seconds and 111 data points per record. The header of each record gives start time, station number, number of A channels (3), number of B channels (3), and digitizing interval for A channels (1 second). It is emphasized that modifications allowing use of B channels for correlation and other complicated numerical manipulations, would be difficult. At present the B channels may be read from the tape at any interval (1 data pt/5 sec, 1 pt/min, 1 pt/hr, and so on) and plotted on any scale. The filters may also be applied directly with the appropriate value of DLT.

Finally, this report will not describe the mathematical justifications for the procedures used, since they have been provided elsewhere (Berg, 1974, 1975).

SYSTEM STRUCTURE

This section discusses the interactions that accomplish data transfer between subroutines.

KREAD, a routine written in ASSEMBLOR, reads data from the tape, 555 seconds' worth (1 record, 6006 bytes) at a time. The data pass to READ through the array AREA. READ interprets the data, forming for each record a header array and six data arrays. The header array, HEAD (10), consists of (1) record number, (2) station number (22 = KIP), (3) year, (4) day, (5) hour, (6) minute, and (7) second of the start time of the data in the record, (8) number of A (velocity) channels, (9) number of B (displacement) channels, and finally (10) spacing in seconds between data points in the A channels. HEAD (7) and HEAD (10) are not integers, so the use of the EQUIVALENCE (HEAD (1), IEAD (1)) statement is helpful.

Beginning with the first records, FIND checks the times in HEAD (3-7) against the desired start time until it finds the correct starting record. FIND calculates the correct record number by subtracting the time in HEAD (3-7) from the desired start time, dividing the result by 555 sec/record and skipping backward or forward by the correct number of records, repeating this process until it reaches the record containing the desired start time. This procedure reduces execution time but becomes unworkable if there is a large gap in the data. Refer to the description of READ for details.

FIND takes records one by one from READ through A1-3 in COMMON/SMACK/ and loads the data into CH1-3. At the end of the FIND subroutine, SHRINK corrects CH1-3 by deleting data from the beginning and end of each channel that are outside the desired time range. CH1-3 are then of equal length and contain vertical, NS, and EW velocity data, respectively. HEAD (3-7) contains the time of the first data point, and IXMAX (COMMON/X/) contains the length of each array. At this point, FIND returns control to the main program. The data in CH1-3 must be despiked by the statement CALL DSPYK(0), after which they are ready for any of the manipulations described below.

ROTATION--This calculation translates NS and EW data into radial (parallel to propagation direction) and transverse (perpendicular to radial), modes (both in plane of surface). Data in CH1, CH2, and CH3 are not changed in any way. Instead, two new arrays (CHR and CHT, radial and transverse) are filled. The parameters required by the subroutine ROTATE are PHI, the azimuthal angle (N through E) between N and the direction of the earthquake epicenter from the receiving station (measured in degrees), and G, the gain of channel A3 relative to channel A2 (EW relative to NS).

FILTERING-- Three zero-phase shift filters are available in this system: high-pass, low-pass, and band-pass, where high and low refer to frequency. The user calls HPFILT, LPFILT, and BPFFILT to calculate the filter coefficients, which he places in the array W whose length is 2*N+1. The user supplies HAMING, which truncates the filters with a Hamming window by changing

the contents of W; and the user supplies N to FLTADJ so that start and stop times supplied to FIND can be modified. DOFILT performs the filtering on one channel at a time and changes the contents of CH1-3, CHR, or CHT. The filtering is done in the time domain by a correlation technique between array W and a data channel the user specifies. This technique deletes N points from each end of the filtered array. DOFILT changes the start time in HEAD (1-10) and the value of IXMAX (if ICHG = 1) so that the correct values of HEAD (10) and IXMAX pass to subsequent programs. ICHG should be set to 1 on the final call to DOFILT.

In addition to calculating filter coefficients, HPFILT, BPFI LT, and LPFILT supply through COMMON/FILT/ a string and periods (in seconds) to the plotting subroutine (PLT1). PLT1 uses for these values the labels of the plot.

FOURIER ANALYSIS--If the user copies the data in any of the channel arrays (CH1-3, CHR, CHT) into a complex array whose imaginary part is zero and whose length is an integral power of 2, FASTO (Fast Fourier Transform) may be used. It replaces the data in the array with the complex Fourier coefficients. The resulting array is symmetric about data point N+1 (Nyquist frequency). The second half of the array will be the complex conjugate of the first. The first data point of the array will contain the mean. AVENUL may be used to zero-mean the data prior to loading the complex array.

PLOTTING--PLT1 is designed to plot a single channel seismogram on a XYNETICS plotter. This subroutine draws the seismogram,

labels the axes, and writes a title underneath the plot. The title includes station number and three-letter abbreviation, and the time of the first data point, all from HEAD (1-10). With appropriate arguments, PLT1 labels the rotation angle and gain factor (from COMMON/ANGLE/), as well as the filter type and corner periods (from COMMON/FILT/). SETXYN or SETCC supply letter size (H1, H2) and distance (XOFF, YOFF) from the starting pen position to the origin of the plot (bottom end of Y-axis) through COMMON/PLTPAR/. After one seismogram is plotted (one XNETICS drawing is generated) PLT1 places the pen above and to the left of the plot. A subsequent call to PLT1 will generate a second trace immediately above the first (if the operator has not moved the pen manually). Thus plots are generated from the bottom upward. To receive the plots in the usual order, the user must plot CH3 first and CH1 last.

PLT1 calls XNETICS subroutines, which are similar to some CALCOMP plotting routines. An output tape is required and each job generates one file on the tape. DTRK must be specified in the JCL for this output tape even though 800 BPI is used. Please read the XNETICS plotting instruction booklet for more details (XNETICS, 1973).

PLT1 can find the maximum and minimum values in the array to be plotted, thus making the plot (without labels) exactly the height specified. PLT1 prints the values it has used. If the station number, HEAD(2), is not in PLT1's list, it prints this number and deletes the station name and number from the label. PLT1 can be used to plot any array, but the horizontal

axis is labelled correctly only if the data points are one second apart and the correct start time has been previously placed in HEAD (3-7). PLTB may be used if the data points are an integer multiple of 5 sec interval.

A printer plot of any array may be generated by PRPLT1. There are no labels, except that each line contains the data point number and its value. One line per array element is printed.

The procedures above apply to A-channel (velocity) information. If the user wishes to read B-channel (displacement) data, he must use FINDB. Here he has the option of specifying the spacing in seconds between successive data points in his final CH1-3 arrays. Rotation and filtering may be applied directly. PLOTB should be used.

CORRELATION--Cross-correlation is accomplished by using several subroutines. A short seismogram segment (<20 min) called the reference is correlated with a longer segment (<45 min) called the scan. Much information may be extracted from this process, but only programming considerations will be discussed here.

The user supplies start and stop times for the reference and the scan, as well as an origin time for the earthquake represented in the reference, through a BLOCK DATA subprogram. He must also calculate any filter before calling COREAD. COREAD then reads scan and reference from the input tape, rotates and/or filters the data if desired, and stores the results in scratch files on the disk. Note that if COREAD is to be used,

FILTADJ, DOFILT, and ROTATE should not be called in the main program. The start and stop times should be those the user wishes to see in the final output plots. COREAD performs all the manipulations of times that are necessitated by time domain correlations.

The user then calls CORRL8, once for each channel. Each call to CORRL8 reads the data from the appropriate scratch file and plots the reference and then the scan. CORRL8 performs the correlation and plots the coefficients. CORRL8 places the output parameters of interest in COMMON/PRINT/ for later listing by TABLE. Finally, it calculates the sum trace. This array (SUM) contains the point-by-point arithmetic mean of all the correlation coefficients produced by CORRL8. For example, if three channels are correlated, each call to CORRL8 adds to the values already in SUM the coefficients calculated by CORRL8, but divided by three. After the user calls CORRL8 three times, SUM will contain the average of three correlations. COREAD initializes SUM to zero. Because of the nature of PLT1, CH3 should be correlated first and CH1 last.

After correlation, a single CALL PLT1 plots the sum trace and all the timing information is correct. CALL TABLE tabulates the results for all channels and CALL WRTSUM writes the sum trace coefficients on disk for later use in beam focusing. At the end of all plotting jobs the statement

CALL PLOT (0, HYT, 999)

should be used. This places an EOF on the output tape and

generates a table showing how many XNETICS drawings have been produced (1 for every CALL PLT1 plus an extra for the EOF), thus checking the correct operation of the program.

BEAM FOCUSING--A further increase in the signal-to-noise ratio for correlation SUM traces may be accomplished by averaging several SUM traces that were created by calls to WRTSUM. This procedure is accomplished by the program SUMAVE, listed in the following section.

GROUND MOTION--Use of the subroutine INFILT with the other filtering subroutines (FLTADJ, DOFILT) allows retrieval of the ground motion by deconvolution of the seismometer and recording system response from the taped seismic data. The response must be stored on disk. The sample program FILTER1 illustrates this procedure.

References

Berg, Eduard, 1974, Rayleigh Waves from High-Gain Long-Period Stations: Signal Extraction; Amplitude Determination; and Separation of Overlapping Wave Trains, Hawaii Inst. Geophys. Report HIG-74-10, 29 pp., 21 computer outputs.

Berg, Eduard, 1975, Rayleigh Waves from High-Gain Long-Period Stations: Signal Extraction; Amplitude Determination; and Separation of Overlapping Wave Trains, Bull. Seismol. Soc. Am., v. 65, no. 6, p. 1761-1778.

Berg, Eduard, and Duncan M. Chesley, Automated High-Precision Amplitude and Phase Calibration of Seismic Systems, Bull. Seismol. Soc. Am., in press.

Lamont-Doherty Geological Observatory, 1971, High-Gain Long-Period Seismograph Station Instrumentation, Vol. 1 and 2, Advanced Research Project Agency Order 1513, 58 pp.

Pomeroy, R. W., G. Hade, J. Savino, and R. Chander, 1969, Preliminary Results High-Gain Wide-Band Long-Period Electromagnetic Seismograph Systems, J. Geophys. Res., v. 74, p. 3295-3298.

XNETICS, 1973, XNETICS Basic Software Fast Mode, XNETICS, Inc., 6710 Variel Ave., Canoga Park, Ca.,

SUBROUTINES

This section contains lists of all the subroutines in the system. There are four types of subroutines:

FILTER: These subroutines calculate filter coefficients and start times, and are used to apply the various filters to the data. Filtering is accomplished using a correlation technique and requires several routines.

UTILITY: These subroutines perform 'bookkeeping'. They usually are short and usually are not found in main programs.

INPUT-OUTPUT (IO): These read tapes, plot, write files, or print results.

DATA: These programs perform the mathematical manipulations, except for filtering.

The following list should be useful for finding the exact order of the arguments of the subroutines.

AVENUL (A, I)
BPFILT (W, N, DLT, BPFREQ, HPFREQ)
COREAD (LREF, PHI, GA)
CORRL8 (ICHAN, SCALE, HYT, LAB, NUMCH)
DOFILT (A, W, N, ICHG)
DSPYK (NUM)
FASTO (A, M, MODE)
FIND (ISTART, ISTOP)
FINDB (ISTART, ISTOP, INTER)
FLTADJ (IL, ISRT, ISTP)
HAMING (W, N)
HDCONV (IHEAD, NUM)
HD2SEC (IA, IB)
HPFILT (W, N, DLT, HPFREQ)
INFILT (ICH, W, N, N1, N2)
KREAD (AREA, NBYTES) or KRDBK (AREA(LAST), NBYTES)
LPFILT (W, N, DLT, BPFREQ)
MAXMIN (A, N, AMAX, MAXJ, AMIN, MINJ)
PLOTB (Z, SCALE, HITE, ZMAX, ZMIN, LKZ, ISPIK, LAB, INTER)
PLT1 (Z, SCALE, HITE, ZMAX, ZMIN, LKZ, ISPIK, LAB)
PRPLT1 (X, LB, LE, LS)
READ (NREC, IPRT)
ROTATE (PHI, G, NUM)
SEC2HD (IB, IA)
SETCC
SETNP

SETXYN

SHRINK (IBEG, IEND)

TABLE

WRTSUM (IF)

NAME--AVENUL

TYPE--DATA

SOURCE--MAREK FRYDRICH

PURPOSE and COMMENTS--subtracts the mean from an array of data

DESCRIPTION--CALL AVENUL (A, I)

where: A is the name of the array

I is the length of the array.

```
ISN 0002      SUBROUTINE AVENUL(A,IXMAX)
ISN 0003      DIMENSION A(1)
ISN 0004      SUM=0.0
ISN 0005      DO 5 I=1,IXMAX
ISN 0006      SUM=SUM+A(I)
ISN 0007      5 CONTINUE
ISN 0008      DO 7 I=1,IXMAX
ISN 0009      A(I)=A(I)-(SUM/IXMAX)
ISN 0010      7 CONTINUE
ISN 0011      RETURN
ISN 0012      END
```

NAME--BPFILT

TYPE--FILTER

SOURCE--D. CHESLEY

PURPOSE--Generates filter coefficients for a band-pass filter.

The filter will be applied by a correlation technique
(DOFILT) in the time domain.

DESCRIPTION--CALL BPFILT (W, N, DLT, BPFREQ, HPFREQ)

where W - the array for the coefficients

N - the number such that $2*N+1$ is the number of
coefficients (≤ 1000)

DLT - the time interval between data points in seconds

BPFREQ - low pass corner frequency (HZ)

HPFREQ - high pass corner frequency (HZ)

This program must be used in conjunction with FLTADJ, DOFILT,
and HAMING.

COMMON--/FILT/ is used by PLT1 for correct labelling of the plot.

```

ISN 0002      SUBROUTINE BPFILT (W,N,DLT,BPFREQ,HPFREQ)
C
C      W IS ARRAY OF 2*N+1 POINTS
C      N IS NUMBER OF DATA POINTS EACH SIDE OF MIDDLE
C
ISN 0003      COMMON/FILT/FILAB(2),SPER,XLPER
ISN 0004      DIMENSION XLAB(2)
ISN 0005      DIMENSION W(1)
ISN 0006      DATA XLAB/'BP F','ILT'/
ISN 0007      SPER=1./HPFREQ
ISN 0008      XLPER=1./BPFREQ
ISN 0009      FILAB(1)=XLAB(1)
ISN 0010      FILAB(2)=XLAB(2)
ISN 0011      PI=3.1415926536
ISN 0012      CON1=DLT*BPFREQ*2.
ISN 0013      CON2=DLT*HPFREQ*2.
ISN 0014      DO 10 I=1,N
ISN 0015      X1=(-N+I-1)*PI*CON1
ISN 0016      X2=(-N+I-1)*PI*CON2
ISN 0017      W(I)=CON1*SIN(X1)/X1-CON2*SIN(X2)/X2
ISN 0018      W(2*N-I+2)=W(I)
ISN 0019      10 CONTINUE
ISN 0020      W(N+1)=CON1-CON2
ISN 0021      RETURN
ISN 0022      END

```

NAME--COREAD

TYPE--IO

SOURCE--D. CHESLEY

PURPOSE--COREAD reads data from tape and creates scratch files
for subsequent access by CORRL8.

DESCRIPTION--CALL COREAD (LREF, PHI, GA)

LREF - If LREF ≠ 0 the program applies a filter to all data .

PHI - angle of rotation

GA - gain factor for rotation

PHI and GA are the arguments of ROTATE. If they are both zero
no rotation is performed.

COMMON--/SEARCH/ - contains data that is read off tape

/COR/ - contains array for sum (average correlation)

trace and times for reference, origin, and scan

/TIME/ - contains lengths of various arrays, start
times of reference and scan, and JUMP, which
indicates the order of the reference and scan
in time

/ANGLE/ - contains data for PLT labels

/TURN/ - contains rotated data

/ARRAY/ - contains filter length and coefficients

/PRINT/ - contains data for TABLE that are initialized
in COREAD

PRECEDING PAGE BLANK NOT FILMED

NOTES--CORRL8 operates on only one channel at a time. To avoid rereading the tape for other channels, COREAD reads the data once and creates scratch files, which are then read by CORRL8. This saves execution time and core requirements but adds three more cards to the JCL stream. Suitable modifications to COREAD enable the user to use other types of reference and scan data. Files may be created by an independent main program and suitable parameters supplied to CORRL8 through COMMON. Similar modifications have been used to allow an average calibration pulse as a reference instead of actual data read from magnetic tape by COREAD. The danger in modifications such as these is that values in COMMON areas may be wrong (such as start times or array sizes); these values should be carefully examined in the event of a program failure. The necessary times are supplied to COREAD from a BLOCK DATA subprogram through COMMON/COR/. IREF1 and IREF2 (dimension = 5, integer) contain year, day, hour, minute, and second of the start and stop times of the reference to be read off tape and used by PLT1 labels. IORIG contains the origin time of the reference earthquake in the same format. ISCAN1 and ISCAN2 contain start and stop times for the scan trace.

The user must supply the JCL for defining the scratch files. See sample programs.

```

ISN 0002      SUBROUTINE COREAD(LREF,PHI,GA)
ISN 0003      COMMON/SEARCH/CH1(5550),CH2(5550),CH3(5550)
ISN 0004      COMMON/COR/SUM(2700),IREF1(5),IREF2(5),IORIG(5),
              •ISCAN1(5),ISCAN2(5)
ISN 0005      COMMON/TIME/NSEC,REFSEC,RFSTRT,SCNSRT,JUMP,ENDSEC
ISN 0006      COMMON/ANGLE/ANG,GAIN
ISN 0007      COMMON/TURN/CHR(5550),CHT(5550)
ISN 0008      COMMON/ARRAY/N,W(1000)
ISN 0009      COMMON/PRINT/JMAX(4),JMIN(4),CMAX(4),CMIN(4),SLOPE1(4),
              •SLOPE2(4),ERROR1(4),ERROR2(4),AMPL1(4),AMPL2(4),AMPER1(4),
              •AMPER2(4)

ISN 0010      C      INTEGER REFSEC,RFSTRT,RFSTOP,SCNSRT,SCNSTP,BEGIN,REFHED
ISN 0011      C      INTEGER SCN1,SCNHED,SCNCHK,END,TSTART,XS,ENDSEC
ISN 0012      C      DIMENSION IEAD(10),IHEAD(5),SCN1(5),IR1(5),IP2(5),IS1(5),IS2(5)

ISN 0013      C      DO 20 J=1,2700
ISN 0014      20     SUM(J)=0.0
ISN 0015      C      JUMP=1
ISN 0016      C      ANG=PHI
ISN 0017      C      GAIN=GA
ISN 0018      C      DO 50 ICHAN=1,4
ISN 0019      C      JMAX(ICHAN)=0
ISN 0020      C      JMIN(ICHAN)=0
ISN 0021      C      CMAX(ICHAN)=-99999.
ISN 0022      C      CMIN(ICHAN)=99999.
ISN 0023      C      SLOPE1(ICHAN)=0.
ISN 0024      C      SLOPE2(ICHAN)=0.
ISN 0025      C      ERROR1(ICHAN)=0.
ISN 0026      C      ERROR2(ICHAN)=0.
ISN 0027      C      AMPL1(ICHAN)=0.
ISN 0028      C      AMPL2(ICHAN)=0.
ISN 0029      C      AMPER1(ICHAN)=0.
ISN 0030      C      AMPER2(ICHAN)=0.
ISN 0031      50     CONTINUE

ISN 0032      C      DO 70 J=1,5
ISN 0033      C      IR1(J)=IREF1(J)
ISN 0034      C      IR2(J)=IREF2(J)
ISN 0035      C      IS1(J)=ISCAN1(J)
ISN 0036      C      IS2(J)=ISCAN2(J)
ISN 0037      70     CONTINUE
ISN 0038      C      IF(LREF.EQ.0)GO TO 90

ISN 0040      71     CONTINUE
ISN 0041      C      CALL FLTADJ(N,IR1,IR2)
ISN 0042      C      CALL FLTADJ(N,IS1,IS2)
ISN 0043      72     CONTINUE
ISN 0044      C      CALL HD2SEC(IR1,IR1 SEC)
ISN 0045      C      CALL HD2SEC(IR2,IR2 SEC)
ISN 0046      C      IRSEC=IR2 SEC-IR1 SEC+1
ISN 0047      C      IF(IRSEC.LE.1510) GO TO 80
ISN 0049      C      XS=IRSEC-1510
ISN 0050      C      PRINT 10,XS
ISN 0051      C      GO TO 440

ISN 0052      80     CALL HD2SEC(IS1,IS1 SEC)
ISN 0053      C      CALL HD2SEC(IS2,IS2 SEC)
ISN 0054      C      ISSEC=IS2 SEC-IS1 SEC+1

ISN 0055      90     CALL HD2SEC(IREF1,RFSTRT)
ISN 0056      C      CALL HD2SEC(IREF2,RFSTOP)
ISN 0057      C      REFSEC=RFSTOP-RFSTRT+1
ISN 0058      C      IF(REFSEC.LE.1510)GO TO 100
ISN 0060      C      XS=REFSEC-1510
ISN 0061      C      PRINT 10,XS
ISN 0062      10     FORMAT(1X,'LENGTH OF REFERENCE EXCEEDS DIMENSION BY ',I7)
ISN 0063      C      STOP
ISN 0064      100    CALL HD2SEC(ISCAN1,SCNSRT)
ISN 0065      C      CALL HD2SEC(ISCAN2,SCNSTP)
ISN 0066      C      NSEC=SCNSTP-SCNSRT+REFSEC
ISN 0067      C      ENDSEC=SCNSTP-SCNSRT+1
ISN 0068      C      IF(LREF.EQ.0) ISSEC=NSEC
ISN 0069      C      IF(LREF.NE.0) ISSEC=ISSEC+REFSEC-1
ISN 0070      C      IF(ISSEC.LE.4210)GO TO 110
ISN 0072

```

```

ISN 0074      XS=ISSEC-4210
ISN 0075      PRINT 11,XS
ISN 0076      FORMAT(1X,'LENGTH OF SCAN EXCEEDS DIMENSION BY ',I7)
ISN 0077      STOP

C               GET REFERENCE FROM TAPE
C
ISN 0078      110 IF (SCNSFT.LT.RFSTRT) JUMP=2
ISN 0080      GO TO (111,200),JUMP
ISN 0081      111 CALL FIND(IR1,IR2)
ISN 0082      CALL DSPYK(0)
ISN 0083      IF(GAIN.NE.0.) CALL ROTATE(PHI,GAIN,0)
ISN 0085      IF(LREF.EQ.0) GO TO 120
ISN 0087      CALL DOFILT(CH1,W,N,0)
ISN 0088      IF(GAIN.NE.0.) GO TO 115
ISN 0090      CALL DOFILT(CH2,W,N,0)
ISN 0091      CALL DOFILT(CH3,W,N,1)
ISN 0092      GO TO 120
ISN 0093      115 CALL DOFILT(CHR,W,N,0)
ISN 0094      CALL DOFILT(CHR,W,N,1)

ISN 0095      120 WRITE(11) CH1
ISN 0096      KUMP=2
ISN 0097      IF(GAIN.NE.0.) GO TO 130
ISN 0099      WRITE(12) CH2
ISN 0100      WRITE(13) CH3
ISN 0101      GO TO (200,350),JUMP
ISN 0102      130 WRITE(12) CHR
ISN 0103      WRITE(13) CHT
ISN 0104      GO TO (200,350),JUMP

ISN 0105      200 CALL HD2SEC(IS1,IS1SEC)
ISN 0106      LEN=IS1SEC+ISSEC-1
ISN 0107      CALL SEC2HD(LEN,IS2)
ISN 0108      CALL FIND(IS1,IS2)
ISN 0109      CALL DSPYK(0)
ISN 0110      IF(GAIN.NE.0.) CALL ROTATE(PHI,GAIN,0)
ISN 0112      IF(LREF.EQ.0) GO TO 220
ISN 0114      CALL DOFILT(CH1,W,N,0)
ISN 0115      IF(GAIN.NE.0.) GO TO 210
ISN 0117      CALL DOFILT(CH2,W,N,0)
ISN 0118      CALL DOFILT(CH3,W,N,1)
ISN 0119      GO TO 220
ISN 0120      210 CALL DOFILT(CHR,W,N,0)
ISN 0121      CALL DOFILT(CHR,W,N,1)

ISN 0122      220 WRITE(11) CH1
ISN 0123      IF(GAIN.NE.0.) GO TO 330
ISN 0125      WRITE(12) CH2
ISN 0126      WRITE(13) CH3
ISN 0127      GO TO (350,111),JUMP
ISN 0128      330 WRITE(12) CHR
ISN 0129      WRITE(13) CHT
ISN 0130      GO TO (350,111),JUMP

ISN 0131      350 CONTINUE
ISN 0132      ENDFILE 11
ISN 0133      REWIND 11
ISN 0134      ENDFILE 12
ISN 0135      REWIND 12
ISN 0136      ENDFILE 13
ISN 0137      REWIND 13
ISN 0138      440 RETURN
ISN 0139      END

```

NAME--CORRL8

TYPE--DATA

SOURCE--D. CHESLEY

PURPOSE-- cross correlation of one array, called the reference, with another, called the scan. Operates on one channel. Successive calls create an average trace that is the arithmetic mean, point by point, of all the calculated correlation coefficients. Each call generates three plots: reference, scan, and correlation coefficients, in that order.

DESCRIPTION-- CALL CORRL8 (ICHAN, SCALE, HYT, LAB, NUMCH)

ICHAN - channel number to be correlated. 1 = CH1, 2 = CH2 or CHR, 3 = CH3 or CHT

SCALE - horizontal scale of plotted output cm/min

HYT - height of plot in inches (from minimum to maximum, not including label)

LAB - plotting label parameters (see PLT1)

= 0 no rotation or filter labels

= 1 rotation, no filter

= 2 filter, no rotation

= 3 rotation and filter labels

NUMCH - number of channels that are combined in sum (average correlation) trace (one CALL CORRL8 for each channel)

COMMON - /SMACK/ contains header information for PLT1 labels

/SEARCH/ contains data and correlation coefficients

/X/ contains lengths of plotted arrays

```
/COR/ contains sum trace and reference, origin, and  
scan times  
/ANGLE/ contains rotation information for PLT1 labels  
/TURN/ contains rotated data  
/PRINT/ contains output for TABLE  
/TIME/ contains lengths of arrays and JUMP, which gives  
order of scan and reference in time
```

NOTES--CORRL8 reads files that have been created by COREAD (or a similar process). There is JCL interaction here. Channel 1 data must be stored in file 11, 2 in 12, and so on (see sample program). CORRL8 plots the reference and then the scan. For correct timing information, the data must be one point per second. CORRL8 performs the correlation, plots the coefficients and calculates correlation amplitudes. CORRL8 divides each coefficient by NUMCH and adds the coefficients to the values in SUM. This results in an average correlation after all correlations are finished. (There must be NUMCH calls to CORRL8). CORRL8 passes the output to TABLE for printing. The sum trace must be plotted by the main program.

```

ISN 0002      SUBROUTINE CORRL8(ICHAN,SCALE,HYT,LAB,NUMCH)
ISN 0003      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),
               .B3(111),HEAD(10),IREC
ISN 0004      COMMON/SEARCH/CH1(5550),CH2(5550),CH3(5550)
ISN 0005      COMMON/X/IXMAX
ISN 0006      COMMON/COR/SUM(2700),IREF1(5),IREF2(5),I0RIG(5),
               .ISCAN1(5),ISCAN2(5)
ISN 0007      COMMON/ANGLE/ANG,GATN
ISN 0008      COMMON/TURN/CHR(5550),CHT(5550)
ISN 0009      COMMON/PRINT/JMAX(4),JMIN(4),CMAX(4),CMIN(4),SLOPE1(4),
               .SLOPE2(4),ERROR1(4),ERROR2(4),AMPL1(4),AMPL2(4),AMPER1(4),
               .AMPER2(4)
ISN 0010      COMMON/TIME/NSEC,REFSEC,RFSTRT,SCNSRT,JUMP,ENDSEC
ISN 0011      DIMENSION LEAD(10),IHEAD(5)
ISN 0012      INTEGER ENDSEC
ISN 0013      INTEGER REFSEC,RFSTRT,SCNSRT,TSTART
ISN 0014      DOUBLE PRECISION SUMX,SUMY,SUMX2,SUMY2,SUMXY,D1,D2,D3
ISN 0015      EQUIVALENCE (IHEAD(1),LEAD(1))

C
ISN 0016      IF(LAB-1)5,5,6
ISN 0017      5      LABE=0
ISN 0018      GO TO 7
ISN 0019      6      LABE=2
ISN 0020      7      JCHAN=ICHAN+10
ISN 0021      IF(JUMP.EQ.2) GO TO 100
ISN 0023      READ(JCHAN) CH1
ISN 0024      READ(JCHAN) CH2
ISN 0025      REWIND JCHAN
ISN 0026      GO TO 125
ISN 0027      100     READ(JCHAN) CH2
ISN 0028      READ(JCHAN) CH1
ISN 0029      REWIND JCHAN

C          PLOT_REFERENCE
C
ISN 0030      125     CALL HDCONV(IREF1,-1)
ISN 0031      IXMAX=REFSEC
ISN 0032      PRINT 130,ICHAN
ISN 0033      130     FORMAT(1X,/,"REFERENCE: CHANNEL A",I1,/1)
ISN 0034      CALL MAXMIN(CH1,IXMAX,REFMAX,MAXJ,PEFMIN,MINJ)
ISN 0035      GO TO(133,135,135),ICHAN
ISN 0036      133     CALL PLT1(CH1,SCALE,HYT,0.,0.,'A1',0,LABE)
ISN 0037      GO TO 200
ISN 0038      135     IF(GAIN.NE.0.) GO TO 138
ISN 0040      GO TO(133,136,137),ICHAN
ISN 0041      136     CALL PLT1(CH1,SCALE,HYT,0.,0.,'A2',0,LABE)
ISN 0042      GO TO 200
ISN 0043      137     CALL PLT1(CH1,SCALE,HYT,0.,0.,'A3',0,LABE)
ISN 0044      GO TO 200
ISN 0045      138     GO TO(133,139,140),ICHAN
ISN 0046      139     CALL PLT1(CH1,SCALE,HYT,0.,0.,'AR',0,LAB)
ISN 0047      GO TO 200
ISN 0048      140     CALL PLT1(CH1,SCALE,HYT,0.,0.,'AT',0,LAB)
ISN 0049      GO TO 200

C          CONVERT HEADER TO DESIRED START TIME
C
ISN 0050      200     CALL SEC2HD(SCNSRT,IHEAD)
ISN 0051      CALL HDCONV(IHEAD,-1)

C          PLOT SCAN
C

```

```

ISN 0052      IXMAX=NSEC
ISN 0053      PRINT 275,ICHAN
ISN 0054      275  FORMAT(1X,/," SCAN: CHANNEL A",I1,/ )
ISN 0055      GO TO (280,281,281),ICHAN
ISN 0056      280  CALL PLT1(CH2,SCALE,HYT,0.,0.,'A1',0,LABE)
ISN 0057      GO TO 300
ISN 0058      281  IF(GAIN,NE,0.) GO TO 285
ISN 0060      GO TO (280,282,283),ICHAN
ISN 0061      282  CALL PLT1(CH2,SCALE,HYT,0.,0.,'A2',0,LABE)
ISN 0062      GO TO 300
ISN 0063      283  CALL PLT1(CH2,SCALE,HYT,0.,0.,'A3',0,LABE)
ISN 0064      GO TO 300
ISN 0065      285  GO TO (280,286,287),ICHAN
ISN 0066      286  CALL PLT1(CH2,SCALE,HYT,0.,0.,'AR',0,LAB)
ISN 0067      GO TO 300
ISN 0068      287  CALL PLT1(CH2,SCALE,HYT,0.,0.,'AT',0,LAB)

C           CONVERT HEADER TO DESIRED START TIME
C
ISN 0069      300  CALL HD2SEC([ORIG,ITIME])
ISN 0070      TSTART=SCNSRT-RFSTRT+ITIME
ISN 0071      CALL SEC2HD(TSTART,IHEAD)
ISN 0072      CALL HDCONV(IHEAD,-1)

C           *** BEGIN CORRELATION ROUTINE ***
C
C           FIRST CALCULATE CONSTANT TERM
C
ISN 0073      SUMX2=0.0
ISN 0074      SUMX=0.0
ISN 0075      DO 325 I=1,REFSEC
ISN 0076      SUMX2=SUMX2+CH1(I)*CH1(I)
ISN 0077      SUMX=SUMX+CH1(I)
ISN 0078      325  CONTINUE

C           D2=REFSEC*SUMX2-SUMX**2
C
C           NOW CALCULATE OTHER TERMS
C
ISN 0080      SUMY=0.0
ISN 0081      SUMY2=0.0
ISN 0082      326  CONTINUE
ISN 0083      DO 400 J=1,ENDSEC
ISN 0084      SUMXY=0.0
ISN 0085      DO 375 I=1,REFSEC
ISN 0086      IF(J,NE,1) GO TO 370
ISN 0088      SUMY=SUMY+CH2(I+J-1)
ISN 0089      SUMY2=SUMY2+CH2(I+J-1)*CH2(I+J-1)
ISN 0090      370  SUMXY=SUMXY+CH1(I)*CH2(I+J-1)
ISN 0091      375  CONTINUE

C           IF(J,EQ,1) GO TO 380
ISN 0092      SUMY=SUMY-SUMYS+CH2(REFSEC+J-1)
ISN 0094      SUMY2=SUMY2-SUMY2S+CH2(REFSEC+J-1)*CH2(REFSEC+J-1)
ISN 0095
ISN 0096      380  SUMYS=CH2(J)
ISN 0097      SUMY2S=CH2(J)*CH2(J)

C           CORRELATION COEFFICIENT
C

```

```

ISN 0098      D1=REF SEC*SUMXY-SUMX*SUMY
ISN 0099      D3=REF SEC*SUMY2-SUMY**2
ISN 0100      CH2(J)=D1/D2*DSORT(D2*D3)
ISN 0101      SUM(J)=SUM(J)+CH2(J)/NUMCH

C              CHECK FOR MAXIMUM AND MINIMUM AND CALCULATE-
C              ERROR AND SLOPE IF NECESSARY
C
ISN 0102      IF(CH2(J).LE.CMAX(ICHAN)) GO TO 390
C
ISN 0104      JMAX(ICHAN)=J+TSTART-1
ISN 0105      CMAX(ICHAN)=CH2(J)
ISN 0106      SLOPE1(ICHAN)=D1/D2
ISN 0107      ERROR1(ICHAN)=DSQRT((D3/D2-SLOPE1(ICHAN)**2)/(REFSEC-2))
C
ISN 0108      390 IF(CH2(J).GE.CMIN(ICHAN)) GO TO 400
ISN 0110      JMIN(ICHAN)=J+TSTART-1
ISN 0111      CMIN(ICHAN)=CH2(J)
ISN 0112      SLOPE2(ICHAN)=D1/D2
ISN 0113      ERROR2(ICHAN)=DSQRT((D3/D2-SLOPE2(ICHAN)**2)/(REFSEC-2))
C
ISN 0114      400 CONTINUE
ISN 0115      401 CONTINUE
ISN 0116      DIF=REF MAX-REF MIN
ISN 0117      AMPL1(ICHAN)=DIF*SLOPE1(ICHAN)
ISN 0118      AMPL2(ICHAN)=DIF*SLOPE2(ICHAN)
ISN 0119      AMPER1(ICHAN)=DIF*ERROR1(ICHAN)
ISN 0120      AMPER2(ICHAN)=DIF*ERROR2(ICHAN)
ISN 0121      402 CONTINUE
C              PLOT RESULTS
C
ISN 0122      IXMAX=ENDSEC
ISN 0123      GO TO (410,420,420),ICHAN
ISN 0124      410 CALL PLT1(CH2,SCALE,HYT,1..-1.,'C1',0,0)
ISN 0125      GO TO 440
ISN 0126      420 IF(GAIN.NE.0.)GO TO 430
ISN 0128      GO TO (410,425,426),ICHAN
ISN 0129      425 CALL PLT1(CH2,SCALE,HYT,1..-1.,'C2',0,0)
ISN 0130      GO TO 440
ISN 0131      426 CALL PLT1(CH2,SCALE,HYT,1..-1.,'C3',0,0)
ISN 0132      GO TO 440
C
ISN 0133      430 GO TO (410,435,436),ICHAN
ISN 0134      435 CALL PLT1(CH2,SCALE,HYT,1..-1.,'CP',0,0)
ISN 0135      GO TO 440
ISN 0136      436 CALL PLT1(CH2,SCALE,HYT,1..-1.,'CT',0,0)
C
ISN 0137      440 RETURN
ISN 0138      END

```

NAME--DOFILT

TYPE--FILTER

SOURCE--D. CHESLEY

PURPOSE--FILTERS an array of time series data using coefficients calculated by BPFLIT, HPFLIT, LPFLIT and HAMING. DOFILT filters with a correlation technique in time domain.

DESCRIPTION--CALL DOFILT (A, W, N, ICHG)

A - the array to be filtered and the array after filtering

W - array containing the filter coefficients

N - 2*N+1 is the number of coefficients (≤ 1000)

ICHG - The correlation technique used in DOFILT changes

the length of the array after the correlation by

dropping N points from each end of the array. ICHG

#0 changes IXMAX and the start time that goes with

the array A.

COMMON--/SMACK/ contains HEAD(10), which contains the start time
of the data

/X/ contains IXMAX, which is the length of A. Both these
quantities are changed by DOFILT if ICHG#0.

NOTES--If the user wants to filter all three A channels, then
the value of IXMAX and the start time in HEAD(10) should
be changed only once. This should be done on the last
call to DOFILT as below:

PRECEDING PAGE BLANK-NOT FILMED

```

CALL HPFILT (W, N, DLT, HPFREQ)

CALL HAMING (W, N)

CALL DOFILT (CH1, W, N, 0)

CALL DOFILT (CH2, W, N, 0)

CALL DOFILT (CH3, W, N, 1).

```

```

ISN 0002      SUBROUTINE DOFILT(A,W,N,ICHG)
ISN 0003      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),
ISN 0004      .B3(111),HEAD(10),IREC
ISN 0005      COMMON/X/IXMAX
ISN 0006      DIMENSION A(1),W(1),IHEAD(5),IEAD(10)
ISN 0007      EQUIVALENCE (HEAD(1),IEAD(1))
ISN 0008      LCHG=ICHG
ISN 0009      IN=1
ISN 0010      N1=N+1
ISN 0011      N2=IXMAX-N
ISN 0012      DO 20 J=N1,N2
ISN 0013      IMIN=J-N
ISN 0014      COEF=0.
ISN 0015      DO 15 I=1,II
ISN 0016      COEF=COEF+W(I)*A(IMIN+I-1)
ISN 0017      15 CONTINUE
ISN 0018      A(J-N)=COEF
ISN 0019      20 CONTINUE
ISN 0020      IF(LCHG) 22,999,22
ISN 0021      22 IXMAX=IXMAX-2*N
ISN 0022      CALL HDCONV(IHEAD,1)
ISN 0023      CALL HD2SEC(IHEAD,IS)
ISN 0024      IS=IS+N*IN
ISN 0025      CALL SEC2HD(IS,IHEAD)
ISN 0026      DO 40 J=1,4
ISN 0027      IEAD(J+2)=IHEAD(J)
ISN 0028      HEAD(7)=IHEAD(5)
ISN 0029      40 IEAD(J+2)=IHEAD(J)
ISN 0030      999 RETURN
END

```

NAME--DSPYK
 TYPE--UTILITY
 SOURCE--D. CHESLEY


PURPOSE--Removes spikes from data, three A channels simultaneously.

DESCRIPTION--CALL DSPYK (NUM)

NUM = 0 is used if the data has been read using FIND; NUM =
 1 if READ has been used to get the data from the tape.

COMMON--/SEARCH/ contains data before and after despiking if NUM = 0
 /SMACK/ contains data if NUM = 1
 /X/ contains length of the data
 /SPIKE/ contains information for PLT1 giving locations
 where spikes have been removed from each channel

NOTES-- DSPYK finds spikes by considering slopes between successive
 data points.



If $s_1 * s_2$ is negative, a peak (either high or low) has been passed.
 If YMIN is the minimum value in the array and YMAX the maximum,
 then the peak is considered a spike if $s_1 * s_2 < -0.1 * (YMAX - YMIN)^2$.
 When a spike is detected at n, the tape data are replaced by a

straight line connecting n-2 with n+2. The program makes several passes through the data (since YMAX and YMIN may change when a spike is removed) until it makes a pass in which no spikes are found. All spikes found in the HGLP station tapes were only three data points long.

Line 104 + 1 is the statement that determines how sharp a peak must be to be considered a spike.

With the appropriate arguments, PLT1 plots an asterisk at the location of each removed spike.

DSPKY operates on the three channels (CH1-3 or A1-3) in a single CALL statement.

```

ISN 0002      SUBROUTINE DSPYK(NUM)
ISN 0003      COMMON/SEARCH/CH1(5550),CH2(5550),CH3(5550)
ISN 0004      COMMON/X/IXMAX
ISN 0005      COMMON/SMAK/A1(555),A2(555),A3(555),B1(111),B2(111),
              •B3(111),HEAD(10),IREC
ISN 0006      COMMON/SPIKE/SPIK1(500),SPIK2(600),SPIK3(500),ICNT1,ICNT2,
ISN 0007      REAL MASTER
ISN 0008      DIMENSION MASTER(500,3), ICNT(3),IEAD(10)
ISN 0009      DIMENSION YMIN(3),YMAX(3),CH(5550,3),XLIM(3)
ISN 0010      EQUIVALENCE (CH(1,1),CH1(1)),(CH(1,2),CH2(1)),
              •(CH(1,3),CH3(1))
ISN 0011      EQUIVALENCE(HEAD(1),IEAD(1)),(MASTER(1,1),SPIK1(1))
ISN 0012      EQUIVALENCE(MASTER(1,2),SPIK2(1)),(MASTER(1,3),SPIK3(1))

C             INITIALIZE
C
ISN 0013      MAXNUM=500
ISN 0014      DO 75 ICH=1,3
ISN 0015      DO 74 J=1,MAXNUM
ISN 0016      74  MASTER(J,ICH)=0
ISN 0017      75  ICNT(ICH)=0
ISN 0018      ISUM2=0
ISN 0019      IF (NUM.NE.1) GO TO 100

C             ROUTINE IF DSPYK IS CALLED FOLLOWING READ
C
ISN 0021      DO 80 J=1,555
ISN 0022      CH1(J)=A1(J)
ISN 0023      CH2(J)=A2(J)
ISN 0024      CH3(J)=A3(J)
ISN 0025      80  CONTINUE
ISN 0026      IXSAVE=IXMAX
ISN 0027      IXMAX=555

C             FIND MAX., MIN., AND MINIMUM SPIKE SIZE
C
ISN 0028      100  DO 102 ICH=1,3
ISN 0029      102  YMIN(ICH)=99999.
ISN 0030      102  YMAX(ICH)=-99999.

C
ISN 0031      DO 105 ICH=1,3
ISN 0032      DO 104 J=1,IXMAX
ISN 0033      YMIN(ICH)=AMIN1(YMIN(ICH),CH(J,ICH))
ISN 0034      YMAX(ICH)=AMAX1(YMAX(ICH),CH(J,ICH))
ISN 0035      104  CONTINUE
ISN 0036      XLIM(ICH)=-.10*(YMAX(ICH)-YMIN(ICH))**2
ISN 0037      105  CONTINUE
ISN 0038      DO 800 ICH=1,3

```

```

C
C      CHECK FOR SPIKES AT BEGINNING OF ARRAY
C
      ISN 0039
      ISN 0040
      ISN 0041
      DO 200 J=2,3
      SLOPE=(CH(J,ICH)-CH(J-1,ICH))*(CH(J+1,ICH)-CH(J,ICH))
      IF (SLOPE.GT.XLIM(ICH)) GO TO 200
      IF (J.EQ.3) CH(5,ICH)=CH(6,ICH)
      DO 110 L=1,4
      CH(L,ICH)=CH(5,ICH)
      ICNT(ICH)=ICNT(ICH)+1
      IF (ICNT(ICH).GT.MAXNUM) GO TO 200
      MASTER(ICNT(ICH),ICH)=J
      200 CONTINUE

C
C      CHECK FOR SPIKES IN MAIN PART OF ARRAY
C
      ISN 0052
      ISN 0053
      ISN 0054
      ISN 0055
      ISN 0056
      ISN 0057
      ISN 0059
      ISN 0060
      ISN 0061
      ISN 0062
      ISN 0063
      ISN 0064
      ISN 0065
      ISN 0067
      ISN 0068
      JXMAX=IXMAX-3
      DO 550 J=4,JXMAX
      J1=J-2
      J2=J+2
      SLOPE=(CH(J,ICH)-CH(J-1,ICH))*(CH(J+1,ICH)-CH(J,ICH))
      IF (SLOPE.GT.XLIM(ICH)) GO TO 550
      DIFF=CH(J+3,ICH)-CH(J-3,ICH)
      XCNT=0.
      DO 300 K=J1,J2
      XCNT=XCNT+1.
      CH(K,ICH)=CH(J-3,ICH)+XCNT*DIFF/6.
      ICNT(ICH)=ICNT(ICH)+1
      IF (ICNT(ICH).GT.MAXNUM) GO TO 550
      MASTER(ICNT(ICH),ICH)=J
      300 CONTINUE
      550 CONTINUE

C
C      CHECK FOR SPIKES IN LAST TWO POINTS IN ARRAY
C
      ISN 0069
      ISN 0070
      ISN 0071
      ISN 0072
      ISN 0073
      ISN 0074
      ISN 0075
      ISN 0077
      ISN 0079
      ISN 0080
      ISN 0081
      ISN 0082
      ISN 0084
      ISN 0085
      ISN 0086
      J1=IXMAX-2
      J2=IXMAX-1
      DO 750 J=J1,J2
      J3=J1-1
      J4=J1+2
      SLOPE=(CH(J,ICH)-CH(J-1,ICH))*(CH(J+1,ICH)-CH(J,ICH))
      IF (SLOPE.GT.XLIM(ICH)) GO TO 750
      IF (J.EQ.J2) CH(J-2,ICH)=CH(J-3,ICH)
      DO 590 L=J3,J4
      CH(L,ICH)=CH(J-2,ICH)
      ICNT(ICH)=ICNT(ICH)+1
      IF (ICNT(ICH).GT.MAXNUM) GO TO 750
      MASTER(ICNT(ICH),ICH)=J
      590 CONTINUE
      750 CONTINUE
      800 CONTINUE

C
C      CHECK IF NO SPIKES WERE REMOVED IN LAST PASS
C
      ISN 0087
      ISN 0088
      ISN 0090
      ISN 0091
      ISN 0092
      ISN 0094
      ISN 0095
      ISN 0096
      ISN 0097
      ISN 0098
      ISUM1=ICNT(1)+ICNT(2)+ICNT(3)
      IF (ISUM1.EQ.1) GO TO 810
      ISUM2=ISUM1
      GO TO 100
      810 IF (NUM.EQ.1) IXMAX=IXSAVE
      ICNT1=ICNT(1)
      ICNT2=ICNT(2)
      ICNT3=ICNT(3)
      RETURN
      END

```

NAME--FASTO

TYPE--DATA

SOURCE--G. FRYER

PURPOSE-- Computes the discrete Fourier transform, either direct or inverse, of a complex array of length 2^m where m is an integer.

DESCRIPTION--CALL FASTO (A, M, MODE)

A - complex array

M - power of two, giving length of A

MODE - direct (MODE = -1) or inverse (MODE = +1)

```

TSN 0002      SUBROUTINE FASTO(A,M,MODE)
C
C      THIS SUBROUTINE COMPUTES THE DISCRETE FOURIER TRANSFORM OF
C      A 2*M SIZE SINGLE PRECISION COMPLEX NUMBER SERIES IN PLACE
C      USING THE COOLEY-TUKEY ALGORITHM.
C      A IS THE COMPLEX NUMBER SERIES.
C      M IS THE POWER OF TWO WHICH GIVES THE NUMBER OF POINTS IN A.
C      MODE IS A NUMBER WHICH DETERMINES WHETHER THE TRANSFORM IS
C      DIRECT (MODE=-1) OR INVERSE (MODE=+1).
C
C      DIMENSION A(1),J(23)
C      COMPLEX A,W,WX,ALM,HOLD
C      NPTS = 2**M
C      INVERT SUBSCRIPT BIT ORDER IN PLACE
C      K = 0
C      DO 1 I = 1,M
C      1 J(I) = 2***(M-I)
C      DO 4 L = 1,NPTS
C      IF (K.LT.L) GO TO 2
C      HOLD = A(L)
C      A(L) = A(K)
C      A(K) = HOLD
C      2 DO 3 I = 1,M
C      II = I
C      IF (K.LT.J(II)) GO TO 4
C      3 K = K-J(II)
C      4 K = K+J(II)
C      COMPUTE TRANSFORM
C      XPI=3.14159265E+00*MODE
C      W = (1.0,0.0)
C      NL = 1
C      DO 30 L = 1,M
C      WX = (1.0,0.0)
C      NL2 = 2*NL
C      DO 20 NSB = 1,NL
C      DO 10 NSUB = NSB,NPTS,NL2
C      NSLB = NSUB+NL
C      ALM = A(NSLB)*WX
C      A(NSLB) = A(NSUB)-ALM
C      10 NSUB = NSUB+1
C      20 NSB = NSB+1
C      30 L = L+1

```

PRECEDING PAGE BLANK-NOT FILMED

```
ISN 0032      10 A(NSUB) = A(NSUB)+ALM
ISN 0033      20 WX = W*WX
ISN 0034      NL = NL*2
ISN 0035      XPI = XPI/2.0
ISN 0036      30 W = CMPLX(COS(XPI),SIN(XPI))
ISN 0037      IF (MODE.EQ.-1) RETURN
C             DIVIDE BY NORMALIZATION FACTOR
ISN 0039      DO 50 I = 1,NPTS
ISN 0040      50 A(I) = A(I)/NPTS
ISN 0041      RETURN
C             END FASTO
ISN 0042      END
```

NAME--FIND

TYPE--IO

SOURCE--D. CHESLEY

PURPOSE-- Reads data tape and returns desired segment of data, A channels only, in COMMON/SEARCH/ with a maximum of 5550 data points.

DESCRIPTION--CALL FIND (ISTART, ISTOP)

ISTART - (dimension = 5, integer) contains year, day, hour, minute, second of first data point desired

ISTOP - (dimension = 5, integer) contains time for last data point

COMMON--/SEARCH/ contains data returned by FIND

CH1 - vertical, CH2-NS, CH3-EW

/SMACK/ - used by READ to supply data to FIND

/X/ - returns length of data in CH1, 2, and 3

NOTES-- FIND locates the desired records on the data tape and calls READ to interpret the tape. FIND then calls SHRINK to eliminate unneeded data. FIND does not despike the data. FIND prints start time of the first record and stop time of the last record, first and last record numbers, and total number of data points (= 555 x numbers of records). These are not the times given by ISTART and ISTOP, but the desired times should be included in the span printed by FIND.

If a record is not readable, FIND replaces missing data with straight lines.

FIND supplies diagnostic messages if an EOF is encountered, or if a record is read more than six times.

```

ISN 0002      SUBROUTINE FIND(ISTART,ISTOP)
ISN 0003      COMMON/SEARCH/CH1(5550),CH2(5550),CH3(5550)
ISN 0004      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),
              •B3(111),HEAD(10),IREC
ISN 0005      COMMON/X/XMAX
ISN 0006      INTEGER RECS,REREAD
ISN 0007      DIMENSION IEAD(10),ISTART(1),ISTOP(1),ITIME1(5),ITIME2(5)
ISN 0008      DIMENSION SAVE(10),RECS(3)
ISN 0009      EQUIVALENCE (IEAD(1),HEAD(1))

ISN 0010      C
ISN 0011      10 DO 10 J=1,3
ISN 0012      RECS(J)=0
ISN 0013      IPT=0
ISN 0014      REREAD=0
ISN 0015      CALL HD2SEC(ISTART,ION)
ISN 0016      CALL HD2SEC(ISTOP,IOFF)
ISN 0017      NUMREC=(IOFF-ION)/555+2
ISN 0018      C
ISN 0019      NREC=IREC+1
ISN 0020      CALL READ(NREC,IPT)
ISN 0021      C
ISN 0022      IF(IEAD(1).NE.-10) GO TO 30
ISN 0023      NREC=IREC-1
ISN 0024      GO TO 20
ISN 0025      30 RECS(3)=RECS(2)
ISN 0026      RECS(2)=RECS(1)
ISN 0027      RECS(1)=IREC
ISN 0028      IF((RECS(1).NE.RECS(3)).AND.(RECS(1).NE.RECS(2))) GO TO 40
ISN 0029      PRINT 12, RECS(1)
ISN 0030      12 FORMAT(1X,' **** RECORD ',15,' REREAD ****')
ISN 0031      REREAD=REREAD+1
ISN 0032      IF(REREAD.LT.6) GO TO 40
ISN 0033      PRINT 13
ISN 0034      13 FORMAT(1X,' **** REREAD THRESHOLD REACHED: EXEC TERMINATED
ISN 0035      STOP
ISN 0036      C
ISN 0037      40 CALL HDCONV(ITIME1,1)
ISN 0038      CALL HD2SEC(ITIME1,IT1)
ISN 0039      ION1=IT1+555
ISN 0040      IF((ION.GE.IT1).AND.(ION.LE.ION1)) GO TO 100
ISN 0041      IS=ION-IT1
ISN 0042      IADD=ISIGN(1,IS)
ISN 0043      IS=IABS(IS)/555
ISN 0044      IF(IS.EQ.0) IS=1
ISN 0045      NREC=IREC+IADD*IS
ISN 0046      IF(NREC.GT.0) GO TO 20
ISN 0047      PRINT 85
ISN 0048      85 FORMAT(1X,' *** WARNING: BEGINNING OF TAPE ***')
ISN 0049      NREC=1
ISN 0050      GO TO 20
ISN 0051      C
ISN 0052      100 IREC1=NREC
ISN 0053      DO 110 J=1,10
ISN 0054      IF((J.EQ.7).OR.(J.EQ.10)) GO TO 108
ISN 0055      SAVE(J)=IEAD(J)
ISN 0056      GO TO 110
ISN 0057      108 SAVE(J)=HEAD(J)
ISN 0058      110 CONTINUE

```

```

      C
ISN 0061      DO 250 K=1,NUMREC
ISN 0062      J1=(K-1)*555
ISN 0063      DO 200 L=1,555
ISN 0064      J2=J1+L
ISN 0065      CH1(J2)=A1(L)
ISN 0066      CH2(J2)=A2(L)
ISN 0067      CH3(J2)=A3(L)
ISN 0068      200 CONTINUE
ISN 0069      IF(K.EQ.NUMREC) GO TO 250
ISN 0070      NREC=NREC+1
ISN 0071      CALL READ(NREC,IPT)
ISN 0072      CONTINUE
ISN 0073      250
      C
ISN 0074      IREC2=IHEAD(1)
ISN 0075      IXMAX=(IREC2-IREC1+1)*555
ISN 0076      DO 260 J=1,4
ISN 0077      260 ITIME2(J)=IHEAD(J+2)
ISN 0078      ITIME2(5)=HEAD(7)
ISN 0079      CALL HD2SEC(ITIME2,IH)
ISN 0080      IH=IH+555
ISN 0081      CALL SEC2HD(IH,ITIME2)
      C
ISN 0082      DO 275 L=1,10
ISN 0083      IF ((L.EQ.7).OR.(L.EQ.10)) GO TO 274
ISN 0084      IHEAD(L)=SAVE(L)
ISN 0085      GO TO 275
ISN 0086      274 HEAD(L)=SAVE(L)
ISN 0087      275 CONTINUE
      C
ISN 0088      DO 350 J=1,IXMAX,555
ISN 0089      IF(CH1(J).NE.400000) GO TO 350
ISN 0090      J1=J-1
ISN 0091      IF (J1.EQ.0) GO TO 310
ISN 0092      H1=CH1(J1)
ISN 0093      H2=CH2(J1)
ISN 0094      H3=CH3(J1)
ISN 0095      GO TO 330
ISN 0096      310 J1=J+555
ISN 0097      IF (J1.GT.IXMAX) GO TO 320
ISN 0098      H1=CH1(J1)
ISN 0099      H2=CH2(J1)
ISN 0100      H3=CH3(J1)
ISN 0101      GO TO 330
ISN 0102      320 H1=0.0
ISN 0103      H2=0.0
ISN 0104      H3=0.0
ISN 0105      C
ISN 0106      320 H1=0.0
ISN 0107      H2=0.0
ISN 0108      H3=0.0
ISN 0109      C
ISN 0110      330 DO 340 J1=1,555
ISN 0111      J2=J+J1-1
ISN 0112      CH1(J2)=H1
ISN 0113      CH2(J2)=H2
ISN 0114      CH3(J2)=H3
ISN 0115      340 CONTINUE
ISN 0116      350 CONTINUE
      C
ISN 0117      400 PRINT 400,IREC1,IREC2,IXMAX,ITIME1,ITIME2
ISN 0118      400 FORMAT(1X,'START RECORD=',I4,' ',STOP RECORD=',I4,'.',I7,
ISN 0119      .' DATA POINTS',I1X,'START TIME=',I4,'/',I3,'/',I2,'::',
ISN 0120      .'I2,'::,I2,'.',STOP TIME=',I4,'/',I3,'/',I2,'::,I2,'::,I2,'/')
ISN 0118      CALL SHRINK(ISTART,ISTOP)
ISN 0119      RETURN
ISN 0120      END

```

NAME--FINDB

TYPE--IO

SOURCE--D. CHESLEY

PURPOSE--Similar to FIND but returns B channels with any desired spacing between successive data points.

DESCRIPTION--CALL FINDB (ISTART, ISTOP, INTER)

ISTART - same as FIND

ISTOP - same as FIND

INTER - desired spacing between data points in seconds.

INTER should be an integer multiple of 5.

COMMON--same as FIND

NOTES--FINDB performs the same function as FIND except that FINDB fills CH1, CH2, and CH3 with B-channel (displacement) data. FINDB does not correct for parity and tape reading errors, thus the user must check the data required from the tape prior to using FINDB.

```

ISN 0002      SUBROUTINE FINDB(ISTART,ISTOP,INTER)
ISN 0003      COMMON/SEARCH/CH1(5550),CH2(5550),CH3(5550)
ISN 0004      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),
              .B3(111),HEAD(10),IREC
ISN 0005      COMMON/X/IXMAX
ISN 0006      INTEGER RECS,REREAD
ISN 0007      DIMENSION IEAD(10),ISTART(1),ISTOP(1),ITIME1(5),ITIME2(5)
ISN 0008      DIMENSION SAVE(10),RECS(3)
ISN 0009      EQUIVALENCE (IEAD(1),HEAD(1))

C          DO 10 J=1,3
ISN 0010      10    RECS(J)=0
ISN 0011      REREAD=0
ISN 0012      NEXT=1
C          CALL HD2SEC(ISTART,ION)
ISN 0013      CALL HD2SEC(ISTOP,IOFF)
ISN 0014      NUMREC=(IOFF-ION)/555+2
ISN 0015      LEN=(IOFF-ION+1)/INTER+1
ISN 0016
ISN 0017
C          NREC=IREC+1
ISN 0018      20    CALL READ(NREC,0)
C          IF(IEAD(1).NE.-10) GO TO 30
ISN 0019      NREC=IREC-1
ISN 0020      GO TO 20
ISN 0022
ISN 0023

```

PRECEDING PAGE BLANK NOT FILMED

```

ISN 0024      30  RECS(3)=RECS(2)
ISN 0025      RECS(2)=RECS(1)
ISN 0026      RECS(1)=IREC
ISN 0027      IF((RECS(1).NE.RECS(3)).AND.(RECS(1).NE.RECS(2))) GO TO 40
ISN 0029      PRINT 12, RECS(1)
ISN 0030      12  FORMAT(1X,' **** RECORD ',15,' REREAD ****')
ISN 0031      REREAD=REREAD+1
ISN 0032      IF(REREAD.LT.6) GO TO 40
ISN 0034      PRINT 13
ISN 0035      13  FORMAT(1X,' **** REREAD THRESHOLD REACHED: EXEC TERMINATED ****')
ISN 0036      STOP

C               40  CALL HDCONV(ITIME1,1)
ISN 0037      CALL HDSEC(ITIME1,IT1)
ISN 0038      ION1=IT1+555
ISN 0039      IF((ION.GE.IT1).AND.(ION.LE.ION1)) GO TO 100
ISN 0040      IS=ION-IT1
ISN 0042      IADD=ISIGN(1,IS)
ISN 0043      IS=IABS(IS)/555
ISN 0044      IF (IS.EQ.0) IS=1
ISN 0045      NREC=IREC+IADD*IS
ISN 0047      IF(NREC.GT.0) GO TO 20
ISN 0048      PRINT 85
ISN 0050      85  FORMAT(1X,' *** WARNING: BEGINNING OF TAPE ***')
ISN 0051      NREC=1
ISN 0052      GO TO 20

C               100 IREC1=NREC
ISN 0054      DO 110 J=1,10
ISN 0055      IF((J.EQ.7).OR.(J.EQ.10)) GO TO 108
ISN 0056      SAVE(J)=IEAD(J)
ISN 0058      GO TO 110
ISN 0059      SAVE(J)=HEAD(J)
ISN 0060      108 CONTINUE
ISN 0061      110

C               100 ISTEP=INTER/5
ISN 0062      IBEG=(ION-IT1)/INTER+ISTEP
ISN 0063      IEND=111
ISN 0064      DO 250 K=1,NUMREC
ISN 0065      DO 200 J1=IBEG,IEND,ISTEP
ISN 0066      IC=J1
ISN 0067      CH1(NEXT)=B1(J1)
ISN 0068      CH2(NEXT)=B2(J1)
ISN 0069      CH3(NEXT)=B3(J1)
ISN 0070      NEXT=NEXT+1
ISN 0071      IF(NEXT.LE.5550) GO TO 195
ISN 0072      PRINT 150
ISN 0074      150 FORMAT(1X,' *** FIND: DESIRED SCAN EXCEEDS DIMENSION ***')
ISN 0075      GO TO 255
ISN 0076      195 IF (NEXT.GT.LEN) GO TO 255
ISN 0077      200 CONTINUE
ISN 0079      IF(K.EQ.NUMREC) GO TO 255
ISN 0080      NREC=IREC+1
ISN 0082      CALL READ(NREC,0)
ISN 0083      201 CONTINUE
ISN 0084      IBEG=ISTEP-IEND+IC
ISN 0085      250 CONTINUE

C               255 IREC2=IEAD(1)
ISN 0087      IXMAX=NEXT-1
ISN 0088      IEAD(1)=SAVE(1)
ISN 0089      IEAD(2)=SAVE(2)
ISN 0090      CALL HDCONV(ISTART,-1)
ISN 0091      IEAD(8)=SAVE(8)
ISN 0092      IEAD(9)=SAVE(9)
ISN 0093      HEAD(10)=SAVE(10)
ISN 0094      PRINT 400,IREC1,IREC2,IXMAX,(ISTART(K),K=1,5),(ISTOP(K),K=1,5)
ISN 0095      400 FORMAT(1X,' START RECORD =',14,', STOP RECORD =',14,', ',17,
ISN 0096      ' DATA POINTS',/,1X,' START TIME =',14,'/',13,'/',12,':',
ISN 0097      ' 12, ::',12,', STOP TIME =',14,'/',13,'/',12,':',12,::',12,/')
ISN 0098      RETURN
END

```

NAME--FLTADJ

TYPE--FILTER

SOURCE--D. CHESLEY

PURPOSE-- Adjusts start and stop times so desired span is still present after the data have been filtered with DOFILT.

DESCRIPTION--CALL FLTADJ (IL, ISRT, ISTP)

IL - length of array containing filter coefficients is 2*IL+1

ISRT - (dimension = 5, integer) contains year, day, hour,

minute, second of desired start time after filtering

ISTP - (dimension = 5, integer) contains desired stop time
after filtering

FLTADJ changes ISRT and ISTP so that more data than desired will be read from the tape. Subsequent filtering with DOFILT will reduce the data scan to the desired length.

```
1SN 0002      SUBROUTINE FLTADJ(IL,ISRT,ISTP)
1SN 0003      DIMENSION ISRT(1),ISTP(1)
1SN 0004      IN=1
1SN 0005      CALL HD2SEC(ISRT,IS)
1SN 0006      IS=IS-IL*IN
1SN 0007      CALL SEC2HD(IS,ISRT)
1SN 0008      CALL HD2SEC(ISTP,IT)
1SN 0009      IT=IT+IL*IN
1SN 0010      CALL SEC2HD(IT,ISTP)
1SN 0011      RETURN
1SN 0012      END
```

NAME--HAMING

TYPE--FILTER

SOURCE-- D. CHESLEY

PURPOSE-- Places a Hamming window on filter coefficients calculated by HPFILT, LPFILT, or BPFILT.

DESCRIPTION--CALL HAMING (W, N)

W - the array (real, single precision) containing filter coefficients to be modified by HAMING.

N - the length of W is 2*N+1

The Hamming window has a very sharp cutoff (60 db/octave).

The coefficients are calculated as:

$$W(I) = W(I) \times 0.54 + 0.46 \cos \left[\frac{(-N+I-1)}{N} \right], I = 1, 2N+1.$$

```

ISN 0002      SUBROUTINE HAMING(W,N)
C           FOR WEIGHTS WITH HAMMING WINDOW
C           CALL HPFILT FIRST
ISN 0003      DIMENSION W(1)
ISN 0004      PI=3.1415926536
ISN 0005      NMAX=2*N+1
ISN 0006      DO 10 I=1,NMAX
ISN 0007      10   W(I)=(0.54+0.46*COS((-N+I-1)*PI/N))*W(I)
ISN 0008      RETURN
ISN 0009      END

```

PRECEDING PAGE BLANK-NOT FILMED

NAME--HDCONV

TYPE--UTILITY

SOURCE--D. CHESLEY

PURPOSE-- converts time array to header array or vice versa.

DESCRIPTION--CALL HDCONV (IHEAD, NUM)

IHEAD- (dimension = 5, integer) contains or will contain
year, day, hour, minute, second

NUM = +1 for loading IHEAD

= -1 for loading header array

COMMON--/SMACK/ contains the header array.

NOTES: The header array HEAD(10) is used to carry start times
from subroutine to subroutine, but user-supplied times are
in arrays such as IHEAD (ISTOP, ISTART in FIND). HDCONV
is used to change one type of array into the other.

```

ISN 0002      SUBROUTINE HDCONV(IHEAD,NUM)
ISN 0003      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),
ISN 0004      .B3(111),HEAD(10),IREC
ISN 0005      DIMENSION TEAD(10),IHEAD(1)
ISN 0006      EQUIVALENCE (TEAD(1),HEAD(1))
ISN 0007      IF (NUM.EQ.-1) GO TO 50
ISN 0008      DO 10 J=1,4
ISN 0009      10  IHEAD(J)=TEAD(J+2)
ISN 0010      IHEAD(5)=HEAD(7)
ISN 0011      GO TO 100
C
ISN 0012      50  DO 75 J=1,4
ISN 0013      75  TEAD(J+2)=IHEAD(J)
ISN 0014      HEAD(7)=IHEAD(5)
ISN 0015      100 RETURN
ISN 0016      END

```

NAME - - HD 2 SEC

TYPE--UTILITY

SOURCE--D. CHESLEY

PURPOSE--converts start and stop times to seconds since 1968

ignoring leap years (and 1-sec WWV (end of the year) corrections).

DESCRIPTION-- CALL HD2SEC (IA, IB)

IA - (dimension = 5, integer) contains year, day, hour,

minute, second, and is not changed by HD2SEC

IB - returned value (integer) in seconds since 1968.

NOTES--SEC2HD performs the opposite function.

```
ISN 0002      SUBROUTINE HD2SEC(IA,IB)
ISN 0003      DIMENSION IA(1)
ISN 0004      IB=(IA(1)-1968)*365*24*3600
ISN 0005      IB=IB+IA(2)*24*3600
ISN 0006      IB=IB+IA(3)*3600+IA(4)*60+IA(5)
ISN 0007      RETURN
ISN 0008      END
```

PRECEDING PAGE BLANK-NOT FILMED

NAME--HPFILT

TYPE--FILTER

SOURCE--D. CHESLEY

PURPOSE-- Generates coefficients for a high-pass filter to be applied by DOFILT.

DESCRIPTION--CALL HPFILT (W, N, DLT, HPFREQ)

W - an array of 2*N+1 points which contains the calculated coefficients

N - 2*N+1 is the number of coefficients (<1000)

DLT - digitizing interval of data to be filtered

HPFREQ - the desired high-pass corner frequency (Hz)

COMMON--/FILT/ contains data for PLT1 labels.

```

ISN 0002      SUBROUTINE HPFILT(W,N,DLT,HPFREQ)
ISN 0003      COMMON/FILT/FILAB(2),SPER,XLPER
ISN 0004      DIMENSION XLAB(2)
C           W IS ARRAY OF 2 N+1 POINTS
C           N IS NUMBER OF DATA POINTS EACH SIDE OF MIDDLE
C
ISN 0005      DIMENSION W(1)
ISN 0006      DATA XLAB/'HP FILT'/
ISN 0007      FILAB(1)=XLAB(1)
ISN 0008      FILAB(2)=XLAB(2)
ISN 0009      SPER=1./HPFREQ
ISN 0010      PI=3.1415926536
ISN 0011      CON=DLT*HPFREQ
ISN 0012      DO 10 I=1,N
ISN 0013      X=(-N+I-1)*PI*CON*2.
ISN 0014      W(I)=-2.*CON
ISN 0015      IF(X.NE.0) W(I)=W(I)*SIN(X)/X
ISN 0016      W(2*N-1)=W(1)
ISN 0017      W(N+1)=1.-2.*CON
ISN 0018      10  CONTINUE
ISN 0019      RETURN
ISN 0020
ISN 0021      END

```

PRECEDING PAGE BLANK-NOT FILMED

NAME-- INFILT

TYPE--FILTER

SOURCE--D. CHESLEY

PURPOSE--Generates coefficients for a filter that (when applied to data by DOFILT) generates original ground motion by deconvolving the instrument response from the seismic data.

DESCRIPTION--CALL INFILT (ICH, W, N, N1, N2)

ICH - channel number of data that will be filtered

1 = Z, 2 = N-S, 3 = E-W

W - array of length $2*N+1$ that contains the calculated coefficients

N - $2*N+1$ is the number of coefficients

N1 - desired first nonzero Fourier coefficient

N2 - desired last nonzero Fourier coefficient

NOTES--INFILT reads 256 Fourier coefficients of each of three instrument response curves (Z, NS, EW) from a disk file (no. 14 in JCL). It then sets data points 1 to N1-1 and N2+1 to 256 equal to zero, takes the inverse FFT, and stores the real part of the result in array W backward in positions W(258) to W(513). It sets the remaining values in W to zero. DOFILT then uses this array as a filter in the standard way to retrieve the ground motion. This ground motion may then be filtered, rotated, and so forth, using the subroutines in this report. Refer to the sample program FILTER1 for an example of the use of this subroutine.

PRECEDING PAGE BLANK-NOT FILMED

```

ISN 0002
ISN 0003
ISN 0004
ISN 0005
ISN 0006
ISN 0007
ISN 0008
ISN 0009
ISN 0010
ISN 0011
ISN 0012
ISN 0013
ISN 0014
ISN 0015
ISN 0016
ISN 0018
ISN 0019
ISN 0020
ISN 0021
ISN 0022
ISN 0023
ISN 0024
ISN 0025
ISN 0026
ISN 0027
ISN 0028
ISN 0029
ISN 0030
ISN 0031
ISN 0032
ISN 0033
ISN 0034
ISN 0035
ISN 0036

      SUBROUTINE INFILT(ICH,W,N,N1,N2)
      COMPLEX D1(256),D2(256),D3(256)
      DIMENSION W(1)
      NTWO=8
      READ(14) D1,D2,D3
      REWIND 14
      DO 5 J=1,256
      GO TO (2,3,4), ICH
      2   D1(J)=1./D1(J)
      GO TO 5
      3   D1(J)=1./D2(J)
      GO TO 5
      4   D1(J)=1./D3(J)
      CONTINUE
      IF(N1.EQ.1) GO TO 10
      N3=N1-1
      DO 10 J=1,N3
      J1=N-J+1
      D1(J)=CMPLX(0.,0.)
      D1(J1)=CMPLX(0.,0.)
      10  CONTINUE
      N4=N2+1
      N5=N-N2
      DO 20 J=N4,N5
      20  D1(J)=CMPLX(0.,0.)
      CALL FASTO(D1,NTWC,1)
      DO 30 J=1,256
      J1=513-J+1
      W(J1)=REAL(D1(J))
      30  CONTINUE
      DO 40 J=1,257
      40  W(J)=0.
      RETURN
      END

```

NAME--KREAD

TYPE--IO

SOURCE--KARL HINCK

PURPOSE--Reads 7TRK data tapes backward or forward 1 record and
returns appropriate error codes in case of read errors.

Called only by READ and data must be interpreted by READ.

DESCRIPTION--CALL KREAD (AREA, NBYTES)

AREA - dimensioned greater than the length of a block on
the tape

NBYTES - number of bytes read. Set to -40000 if EOF is
encountered. Set to -50000 for a read error. An
error message is placed in the first 50 bytes of AREA

CALL KRDBK (AREA(LAST), NBYTES)

AREA (LAST) is the end of array AREA

NBYTES - returns 0 if correct

CALL KREAD reads next record on tape

CALL KRDBK backspaces tape one record.

BEST AVAILABLE COPY

56

KREAD CSECT
*
* KREAD IS CALLED FROM A FORTRAN PROGRAM AS: CALL KREAD(AREA,NBYTES)...
* AREA MUST BE => BLKSIZE. NBYTES IS THD NUMBER OF BYTES READ IN....
* FOR END OF FILE NBYTES IS SET TO -40000. FOR A READ ERROR IT IS SETTO
* -50000 AND AN ERROR MESSAGE IS PLACED IN THE FIRST 50 BYTES OF AREA..
* TO BACKSPACE: CALL KRDBK(AREA(LAST),NBYTES). HERE THE 1ST ARG. MUST
* BE THE END OF THE ARRAY AND NBYTES IS 0 IF O.K...
* AFTER THE END OF DATA IS INDICATED, CALLING KREAD AGAIN WILL START AT
* THE BEGINNING AGAIN... ONLY TAPES CAN BE READ BACKWARDS, ANYTHING
* ELSE WILL BE READ FORWARDS.
*
* HIG DEPT OF GEOPHYSICS..... KARL HINCK.... 15MAY74
*
 USING KREAD,15
 MVC SW1,ADOR
 BAL 15,SAVE
 USING *,15
KRDBK
 MVC SW1,ARDBK
 SAVE (14,12)
 DROP 15
 USING KRDBK,4
 LR 4,15
 LA 2,SA
 ST 2,8(13)
 ST 13,SA+4
 LR 13,2
 L 2,SW1
 BR 2
OPEN
 LR 3,1
 LA 2,WOPEN
 ST 2,ADOR
 OPEN INTAPE
 LR 1,3
WOPEN
 LM 2,3,0(1)
 READ CHKT,SF,INTAPE,(2),'S'
 CHECK CHKT
CALC
 C 2,F' -50000'
 BE BACK
 L 2,INTAPE+68
 LH 2,22(2)
 LNR 2,2
 AH 2,INTAPE+62
 ST 2,0(3)
 L 13,SA+4
 RETURN (14,12),T,RC=0
SA
 DS 18F
SW1
 DS F
ADOR
 DC A(DOPEN)
ARDBK
 DC A(READBK)
INTAPE
 DCB DSORG=PS,MACRF=(R),EODAD=ENDR,DDNAME=INTAPE,SYNAD=TAPERR
ENDR
 L 2,F' -40000'
 CLOSE INTAPE
 LA 1,OPEN
 ST 1,ADOR
 B BACK
TAPERR
 SYNADAF ACSMETH=BSAM
 ST 14,R14S
 MVC 0(50,2),75(1)
 L 2,F' -50000'
 SYNADRLS
 L 14,R14S
 BR 14
R14S
 DS F
*
READBK
 ENTRY KRDBK
 LM 2,3,0(1)
 READ CHKTBK,SB,INTAPE,(2),
 CHECK CHKTBK
 B CALC
 END

BEST AVAILABLE COPY

NAME--LPFILT

TYPE--FILTER

SOURCE--D. CHESLEY

PURPOSE--calculates low-pass filter coefficients for use by
DOFILT.

DESCRIPTION--CALL LPFILT (W, N, DLT, BPFRQ)

W - array containing calculated filter coefficients

N - length of W is 2*N+1 (<1000)

DLT - digitizing interval of array to be filtered

BPFRQ - low pass corner frequency (Hz)

COMMON/FILT/contains data for PLT1 labels.

```

ISN 0002      SUBROUTINE LPFILT(W,N,DLT,BPFRQ)
ISN 0003      COMMON/FILT/FILAB(2),SPER,XLPER
ISN 0004      DIMENSION XLAB(2)
ISN 0005      DIMENSION W(1)
ISN 0006      DATA XLAB/'LP F',ILT'/
ISN 0007      FILAB(1)=XLAB(1)
ISN 0008      FILAB(2)=XLAB(2)
ISN 0009      XLPER=1./BPFRQ
ISN 0010      PI=3.1415926536
ISN 0011      CON=DLT*BPFRQ
ISN 0012      DO 10 I=1,N
ISN 0013      X=(-N+I-1)*PI*CON*2.
ISN 0014      W(I)=2.*CON
ISN 0015      W(I)=W(I)*SIN(X)/X
ISN 0016      W(2+N-I+2)=W(I)
ISN 0017      10 CONTINUE
ISN 0018      W(N+1)=2.*CON
ISN 0019      RETURN
ISN 0020      END

```

NAME--MAXMIN

TYPE--UTILITY

SOURCE--D. CHESLEY

PURPOSE--finds the location and value of maximum and minimum
in an array.

DESCRIPTION--CALL MAXMIN (A, N, AMAX, MAXJ, AMIN, MINJ)

A - array to be scanned (real, single precision)

N - length of A

AMAX (AMIN) - returned maximum (minimum) value in A

MAXJ (MINJ) - returned data point number of maximum
(minimum)

```

1SN 0002      SUBROUTINE MAXMIN(A,N,AMAX,MAXJ,AMIN,MINJ)
1SN 0003      DIMENSION A(1)
1SN 0004      AMAX=-9999999.
1SN 0005      AMIN=9999999.
1SN 0006      DO 100 J=1,N
1SN 0007      IF(A(J).LE.AMAX) GO TO 50
1SN 0009      MAXJ=J
1SN 0010      AMAX=A(J)
1SN 0011      50  IF(A(J).GE.AMIN) GO TO 100
1SN 0013      MINJ=J
1SN 0014      AMIN=A(J)
1SN 0015      100 CONTINUE
1SN 0016      RETURN
1SN 0017      END

```

PRECEDING PAGE BLANK-NOT FILMED

NAME--PLOTB

TYPE--IO

SOURCE--D. CHESLEY

PURPOSE--Plots B-channel seismic data with an arbitrary (but multiple of 5) number of seconds between data points.

DESCRIPTION--CALL PLOTB (Z, SCALE, HITE, ZMAX, ZMIN, LKZ, ISPIK, LAB, INTER)

Z through LAB - identical to arguments for PLT1

INTER - spacing between data points in seconds (must be multiple of 5)

NOTES-- Operates exactly the same as PLT1 except that INTER must be specified.

```

ISN 0002      SUBROUTINE PLTB(Z,SCALE,HITE,ZMAX,ZMIN,LKZ,ISPIK,LAB,INTER)
ISN 0003      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),
ISN 0004      .B3(111),HEAD(10),IREC
ISN 0005      COMMON/PLTPAR/XOFF,YOFF,H1,H2
ISN 0006      COMMON/X/XMAX
ISN 0007      COMMON/SPIKE/SPIK1(500),SPIK2(500),SPIK3(500),ICNT1,ICNT2,ICNT3
ISN 0008      COMMON/ANGLE/ANG,GAIN
ISN 0009      DIMENSION IEAD(10),Z(1)
ISN 0010      DIMENSION X(5550),Y(5550)
ISN 0011      LOGICAL*4 IIHR/:00 /
ISN 0012      EQUIVALENCE (HEAD(1),IEAD(1))
ISN 0013      KKL=LKZ
ISN 0014      YMAX=ZMAX
ISN 0015      YMINT=ZMIN
ISN 0016      XMAX=IXMAX
ISN 0017      PPM=60./INTER
ISN 0018      XLEN=XMAX*SCALE/(2.54*PPM)
ISN 0019      XXLEN=XLEN+XOFF
ISN 0020      XSCAL=XLEN/XMAX
IF(ZMAX.NE.7MIN) GO TO 301
C
C      FIND MAXIMUM AND MINIMUM VALUES IN ARRAY
C
ISN 0022      YMAX=-99999.
ISN 0023      YMINT=99999.
ISN 0024      DO 300 J=1,IXMAX
ISN 0025      YMAX=AMAX1(Z(J),YMAX)
ISN 0026      YMINT=AMIN1(Z(J),YMINT)
ISN 0027      300  CONTINUE
ISN 0028      PRINT 299,YMIN,YMAX
ISN 0029      299  FORMAT(1HO,'PLT1: MINIMUM= ',F9.2,3X,'MAXIMUM= ',F9.2//)
C
C      SCALE PLCT AND GENERATE ARRAYS TO BE PLOTTED
C
ISN 0030      301  YYMIN=YMIN

```

PRECEDING PAGE BLANK-NOT FILMED

```

ISN 0031      YYMAX=YMAX
ISN 0032      YMAX=YMAX-YMIN
ISN 0033      YMIN=0.
ISN 0034      YSCAL=HITE/YMAX
ISN 0035      YMEAN=YMAX*YSCAL/2.+YOFF
ISN 0036      DO 500 J=1,IXMAX
ISN 0037      X(J)=(J-1)*XSCAL+XOFF
ISN 0038      Y(J)=YSCAL*(Z(J)-YYMIN)+YOFF
ISN 0039      500 CONTINUE
C
C          PLOT Y VS. X
C
ISN 0040      501 CONTINUE
ISN 0041      CALL PLOT(X(1),Y(1),3)
ISN 0042      DO 510 J=2,IXMAX
ISN 0043      510 CALL PLOT(X(J),Y(J),2)
ISN 0044      CALL PLOT(XXLEN,YMEAN,3)
ISN 0045      CALL PLCT(XOFF,YMEAN,2)
C
C          PLOT AND LABEL ONE TICK MARK EVERY 3 CM.
C
ISN 0046      IHR=IEAD(5)
ISN 0047      REM=HEAD(7)
ISN 0048      XS=(60.-REM)*XSCAL*PPM/60.+XOFF
ISN 0049      NMIN=XMAX/PPM
ISN 0050      NMIN=NMIN+1
ISN 0051      XINCR=XSCAL*PPM
ISN 0052      UMEAN=YMEAN+.125
ISN 0053      BMEAN=UMEAN-0.25
ISN 0054      YY=BMEAN-.1
ISN 0055      MIN=IEAD(6)
ISN 0056      XMINS=0.0
C
ISN 0057      DO 600 J=1,NMIN
ISN 0058      K=J-1
ISN 0059      XMIN=XS+XINCR*K
ISN 0060      IF(MIN.EQ.59) GO TO 520
ISN 0062      IF((XMIN-XMINS).GE.(3./2.57)) GO TO 520
ISN 0064      MIN=MIN+1
ISN 0065      GO TO 600
C
ISN 0066      520 XMINS=XMIN
ISN 0067      IF(XMIN.GT.XXLEN) GO TO 600
ISN 0069      CALL PLOT(XMIN,UMEAN,3)
ISN 0070      CALL PLOT(XMIN,BMEAN,2)
ISN 0071      XX=XMIN-.05
ISN 0072      MIN=MIN+1
ISN 0073      IF(MIN.NE.60) GO TO 550
ISN 0075      IHR=IHR+1
ISN 0076      IF(IHR.EQ.24) IHR=0
ISN 0078      XXX=XX-.18
ISN 0079      XIHR=IHR
ISN 0080      CALL NUMBER(XXX,YY,H1,XIHF,0.,-1)
ISN 0081      CALL SYMBOL(XX,YY,H1,IIHR,0.,3)
ISN 0082      MIN=0
ISN 0083      GO TO 600
ISN 0084      550 WMIN=MIN
ISN 0085      CALL NUMBER(XX,YY,H1,WMIN,0.,-1)
ISN 0086      600 CONTINUE
ISN 0087      601 CONTINUE
C
C          PLOT *'S AT LOCATIONS WHERE SPIKES WERE REMOVED
C
ISN 0088      IF(ISPIK.EQ.0) GO TO 675
ISN 0090      IF(ISPIK.EQ.1) ICNT=ICNT1
ISN 0092      IF(ISPIK.EQ.2) ICNT=ICNT2
ISN 0094      IF(ISPIK.EQ.3) ICNT=ICNT3
ISN 0096      IF(ICNT.EQ.0) GO TO 675
ISN 0098      DO 650 I=1,ICNT
ISN 0099      II=ICNT-I+1
ISN 0100      IF(ISPIK.EQ.1) W=(SPIK1(II)-1)*XSCAL
ISN 0102      IF(ISPIK.EQ.2) W=(SPIK2(II)-1)*XSCAL
ISN 0104      IF(ISPIK.EQ.3) W=(SPIK3(II)-1)*XSCAL
ISN 0106      W=W+XOFF
ISN 0107      YWHITE=HITE+YOFF
ISN 0108      CALL SYMBOL(W,YWHITE,H1,11,0.,-1)
ISN 0109      650 CONTINUE
ISN 0110      651 CONTINUE
C
C          PLCT HEADER INFO
C

```

```

ISN 0111      675  CONTINUE
ISN 0112      XL=1.5
ISN 0113      YL=0.07
ISN 0114      IF(IEAD(2).EQ.22) GO TO 700
ISN 0116      IF(IEAD(2).EQ.25) GO TO 701
ISN 0118      IF(IEAD(2).EQ.24) GO TO 702
ISN 0120      IF(IEAD(2).EQ.1) GO TO 703
ISN 0122      IF(IEAD(2).EQ.23) GO TO 704
ISN 0124      IF(IEAD(2).EQ.2) GO TO 705
ISN 0126      IF(IEAD(2).EQ.4) GO TO 706
ISN 0128      PRINT 699,IEAD(2)
ISN 0129      699  FORMAT(1X,'STATION I.D. NC. IS: ',I5)
ISN 0130      GO TO 725
ISN 0131      CALL SYMBOL(XL,YL,H2,'STATION: (22) KIP.',0.,18)
ISN 0132      GO TO 725
ISN 0133      701  CALL SYMBOL(XL,YL,H2,'STATION: (25) MAT.',0.,18)
ISN 0134      GO TO 725
ISN 0135      702  CALL SYMBOL(XL,YL,H2,'STATION: (24) ZLP.',0.,18)
ISN 0136      GO TO 725
ISN 0137      703  CALL SYMBOL(XL,YL,H2,'STATION: (01) CTA.',0.,18)
ISN 0138      GO TO 725
ISN 0139      704  CALL SYMBOL(XL,YL,H2,'STATION: (23) ALQ.',0.,18)
ISN 0140      GO TO 725
ISN 0141      705  CALL SYMBOL(XL,YL,H2,'STATION: (02) CHG.',0.,18)
ISN 0142      GO TO 725
ISN 0143      706  CALL SYMBOL(XL,YL,H2,'STATION: (04) TLO.',0.,18)
ISN 0144      725  XL=XL+19.*6.*H2/7.
ISN 0145      726  CONTINUE
ISN 0146      CALL SYMBOL(XL,YL,H2,'CH:',0.,3)
ISN 0147      XL=XL+3.*6.*H2/7.
ISN 0148      CALL SYMBOL(XL,YL,H2,KKL,0.,2)
ISN 0149      XIN=IEAD(3)
ISN 0150      POS=6.*4.*H2/7.+XL
ISN 0151      CALL NUMBER(POS,YL,H2,XIN,0.,-1)
ISN 0152      CALL WHERE(RETX,RETY,RETFAC)
ISN 0153      POS=RETX
ISN 0154      XIN=-IEAD(4)
ISN 0155      CALL NUMBER(POS,YL,H2,XIN,0.,-1)
ISN 0156      CALL WHERE(RETX,RETY,RETFAC)
ISN 0157      POS=RETX+6.*H2/7.*2.
ISN 0158      XIN=IEAD(5)
ISN 0159      CALL NUMBER(POS,YL,H2,XIN,0.,-1)
ISN 0160      CALL WHERE(RETX,RETY,RETFAC)
ISN 0161      POS=RETX
C
ISN 0162      C   IF(IEAD(6).NE.0) GO TO 735
ISN 0164      CALL SYMBOL(POS,YL,H2,IIHR,0.,4)
ISN 0165      POS=POS+4.*6.*H2/7.
ISN 0166      GO TO 738
C
ISN 0167      735  CALL SYMBOL(POS,YL,H2,122,0.,-1)
ISN 0168      CALL WHERE(RETX,RETY,RETFAC)
ISN 0169      POS=RETX
ISN 0170      XIN=IEAD(6)
ISN 0171      CALL NUMBER(POS,YL,H2,XIN,0.,-1)
ISN 0172      CALL WHERE(RETX,RETY,RETFAC)
ISN 0173      POS=RETX
C
ISN 0174      738  IF(HEAD(7).NE.0.) GO TO 740
ISN 0176      CALL SYMBOL(POS,YL,H2,IIHR,0.,4)
ISN 0177      GO TO 742
C
ISN 0178      740  CALL SYMBOL(POS,YL,H2,122,0.,-1)
ISN 0179      CALL WHERE(RETX,RETY,RETFAC)
ISN 0180      POS=RETX
ISN 0181      IIN=HEAD(7)
ISN 0182      XIN=ITN
ISN 0183      CALL NUMBER(POS,YL,H2,XIN,0.,-1)
ISN 0184      IF(LAB.EQ.0) GO TO 750
C
C          LABEL ROTATION INFO
C
ISN 0186      POS=POS+.75
ISN 0187      CALL SYMBOL(POS,YL,H2,'ANGLE:',0.,6)
ISN 0188      IPHI=ANG
ISN 0189      XANG=ANG

```

```

ISN 0190      POS=POS+6.*6.*H2/7.
ISN 0191      CALL NUMBER(POS,YL,H2,XANG,0..1)
ISN 0192      CALL WHERE(RETX,RETY,RETFAC)
ISN 0193      POS=RETX
ISN 0194      CALL SYMBOL(POS,YL,H2,*DEG.*,0..4)

C
ISN 0195      POS=POS+4.*6.*H2/7.
ISN 0196      CALL SYMBOL(POS,YL,H2,*GAIN FACTOR:*.0..12)
ISN 0197      POS=POS+12.*6.*H2/7.
ISN 0198      XGAIN=GAIN
ISN 0199      CALL NUMBER(POS,YL,H2,XGAIN,0..4)
ISN 0200      CALL WHERE(RETX,RETY,RETFAC)
ISN 0201      POS=RETX
ISN 0202      CALL SYMBOL(POS,YL,H2,*X A3*,0..4)

C
C          PLOT AND LABEL Y-AXIS
C

ISN 0203      750  CONTINUE
ISN 0204      751  CONTINUE
ISN 0205      HYTE=YMIN*YSCAL
ISN 0206      YINCR=YMAX/5.
ISN 0207      NUMDEC=-1
ISN 0208      IF(YINCR.LT.5.) NUMDEC=2
ISN 0210      DO 800 J=1,6
ISN 0211      XK=J-1
ISN 0212      YYY=XK*YINCR*YSCAL+YOFF
ISN 0213      CALL PLOT(0.875,YYY,3)
ISN 0214      CALL PLOT(1.125,YYY,2)
ISN 0215      XYPOS=YYMIN+YINCR*XK
ISN 0216      CALL NUMBER(0.6,YYY,H1,XYPOS,0..NUMDEC)
ISN 0217      800  CONTINUE
ISN 0218      YYMIN=YMIN+YOFF
ISN 0219      YWHITE=YHITE+YOFF
ISN 0220      CALL PLOT(1.,YYMIN,3)
ISN 0221      CALL PLOT(1.,YWHITE,2)
ISN 0222      CALL PLOT(0.,YWHITE,-3)
ISN 0223      CALL PLOT(0.,0..5)
ISN 0224      801  CONTINUE
ISN 0225      RETURN
ISN 0226      END

```

NAME--PLT1

TYPE--IO

SOURCE--D. CHESLEY

PURPOSE--Plots seismic data on a XYNETICS plotter. Labels each plot with station name and code, start time, rotation, and filter information. Data points must be one per second.

DESCRIPTION--CALL PLT1 (Z, SCALE, HITE, ZMAX, ZMIN, LKZ, ISPIK, LAB)

Z - the array to be plotted

SCALE - horizontal scale in cm/min

HITE - height of the plot (without labels) in inches

ZMAX - maximum value of Y-axis

ZMIN - minimum value of Y-axis

LKZ - two-character string enclosed in apostrophes, used to label the channel that is plotted ('A1', 'A2', 'SM')

ISPIK - channel number (1, 2, or 3 for A1, A2, A3 respectively) causes asterisks to be plotted at each location where DSPYK has removed a spike. ISPIK = 0 means no asterisks are plotted.

LAB - label parameter:

0 - no rotation and no filter

1 ~ rotation but no filter

2 ~ filter but no rotation

3 ~ both filter and rotation information are plotted in the label

COMMON--/SMACK/ contains HEAD(10), which holds the start time
of the trace

/PLTPAR/ holds letter sizes and X and Y offsets (see SET)

/FILT/ contains filter information for label

/X/ contains length of Z

/SPIKE/ contains positions of spikes which were removed
by DSPYK

/ANGLE/ contains rotation information for label

NOTES-- PLT1 is designed specifically for plotting A-channel
data at 1 data point per second. HEAD(1-10) contains the
start time. PLT1 plots and labels minute marks, except
that PLT1 suppresses the marks if they are less than three
centimeters from the previous mark, to avoid overcrowding.
Hour marks are always plotted. PLT1 interprets the station
number, HEAD(2), if possible and labels the plot with a
three-letter abbreviation. If the station number is not
decodable it is printed and that portion of the plot label
is deleted. With the appropriate value of LAB, the subrou-
tine includes rotation and/or filter information in the
label. The Y-axis is labelled automatically. If the year
(IEAD(3)) is zero the time is not plotted. The desired
maximum and minimum values to be plotted may be defined in
the argument list (ZMAX, ZMIN), and thus the vertical scale
is user-determined. However, if ZMAX = ZMIN, PLT1 scans
the array and uses the maximum and minimum values in the
array to define the vertical scale. In this case the
maximum and minimum are printed.

The starting position of the pen is (-XOFF, -OFF-H2) from the lower end of the Y-axis. The final position is (-XOFF, HITE+H2). Changes in SCALE and HITE will not affect the letter size.

PLT1 requires the statement CALL SETXYN (or SETCC) prior to the plotting command and the statement

CALL PLOT (0, HITE, 999)

at the end of the main program. An output tape must be supplied. See the sample programs for JCL details.

CALL PLT1 generates ones XNETICS drawing.

```

ISN 0002      SUBROUTINE PLT1 (Z,SCALE,HITE,ZMAX,ZMIN,LKZ,ISPIK,LAB)
ISN 0003      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),
ISN 0004      B3(111),HEAD(10),IREC
ISN 0005      COMMON/PLTPAR/XOFF,YOFF,H1,H2
ISN 0006      COMMON/FILT/FILAB(2),SPER,XLPER
ISN 0007      COMMON/X/IXMAX
ISN 0008      COMMON/SPIKE/SPIK1(500),SPIK2(500),SPIK3(500),ICNT1,ICNT2,ICNT3
ISN 0009      COMMON/ANGLE/ANG,GAIN
ISN 0010      DIMENSION IEAD(10),Z(1)
ISN 0011      DIMENSION X(5550),Y(5550)
ISN 0012      LOGICAL*4 FILAB
ISN 0013      LOGICAL*4 ITHR//:00 '
ISN 0014      EQUIVALENCE (HEAD(1),IEAD(1))
ISN 0015      WTH=6.*H2/7.
ISN 0016      ZERO=0.
ISN 0017      KKL=LKZ
ISN 0018      YMAX=ZMAX
ISN 0019      YMIN=ZMIN
ISN 0020      XMAX=IXMAX
ISN 0021      XLEN=XMAX*SCALE/(2.54*60.)
ISN 0022      XXLEN=XLEN+N*XOFF
ISN 0023      XSCAL=XLEN/XMAX
IF(ZMAX.NE.ZMIN) GO TO 301

C          FIND MAXIMUM AND MINIMUM VALUES IN ARRAY
C
ISN 0025      YMAX=-99999.
ISN 0026      YMIN=99999.
ISN 0027      DO 300 J=1,IXMAX
ISN 0028      YMAX=AMAX1(Z(J),YMAX)
ISN 0029      YMIN=AMIN1(Z(J),YMIN)
ISN 0030      CONTINUE
ISN 0031      PRINT 299,YMIN,YMAX
ISN 0032      299  FORMAT(1HO,'PLT1: MINIMUM= ',E9.3,3X,'MAXIMUM= ',E9.3//)
C          SCALE PLOT AND GENERATE ARRAYS TO BE PLOTTED
C
ISN 0033      301  YYMIN=YMIN
ISN 0034      YYMAX=YMAX
ISN 0035      YMAX=YMAX-YMIN
ISN 0036      YMIN=0.
ISN 0037      YSCAL=HITE/YMAX
ISN 0038      YMEN=YMAX*YSCAL/2.+YOFF
ISN 0039      DO 500 J=1,IXMAX
ISN 0040      X(J)=(J-1)*XSCAL+XOFF
ISN 0041      Y(J)=YSCAL*(Z(J)-YYMIN)+YOFF
ISN 0042      500  CONTINUE

```

```

C
C      PLOT Y VS. X
C
ISN 0043      501  CONTINUE
ISN 0044      CALL PLOT(X(1),Y(1),3)
ISN 0045      DO 610 J=2,IXMAX
ISN 0046      CALL PLOT(X(J),Y(J),2)
ISN 0047      CALL PLOT(XXLEN,YMEAN,3)
ISN 0048      CALL PLOT(XOFF,YMEAN,2)

C
C      PLUT AND LABEL ONE TICK MARK EVERY 3 CM.
C
ISN 0049      IHR=IHEAD(5)
ISN 0050      REM=HEAD(7)
ISN 0051      XS=(60.-REM)*XSCAL+XOFF
ISN 0052      NMIN=XMAX/60.
ISN 0053      NMIN=NMIN+1
ISN 0054      XINCR=XSCAL*60.
ISN 0055      UMEAN=YMEAN+.125
ISN 0056      BMEAN=UMEAN-.25
ISN 0057      YY=BMEAN-.1
ISN 0058      MIN=IHEAD(6)
ISN 0059      XMINS=0.0

C
ISN 0060      DO 600 J=1,NMIN
ISN 0061      K=J-J
ISN 0062      XMIN=XS+XINCR*K
ISN 0063      IF(MIN.EQ.59) GO TO 520
ISN 0065      IF((XMIN-XMINS).GE.(3./2.57)) GO TO 520
ISN 0067      MIN=MIN+1
ISN 0068      GO TO 600

C
ISN 0069      520  XMINS=XMIN
ISN 0070      IF(XMIN.GT.XXLEN) GO TO 600
ISN 0072      CALL PLOT(XMIN,UMEAN,3)
ISN 0073      CALL PLOT(XMIN,BMEAN,2)
ISN 0074      XX=XMIN-.05
ISN 0075      MIN=MIN+1
ISN 0076      IF(MIN.NE.60) GO TO 550
ISN 0078      IHR=IHR+1
ISN 0079      IF(IHR.EQ.24) IHR=0
ISN 0081      XXX=XX-.18
ISN 0082      XIHR=IHR
ISN 0083      CALL NUMBER(XXX,YY,H1,XIHR,0..-1)
ISN 0084      CALL SYMBOL(XX,YY,H1,IIHR,0..3)
ISN 0085      MIN=0
ISN 0086      GO TO 600
ISN 0087      550  WMIN=MIN
ISN 0088      CALL NUMBER(XX,YY,H1,WMIN,0..-1)
ISN 0089      600  CONTINUE
ISN 0090      601  CONTINUE

C
C      PLOT *'S AT LOCATIONS WHERE SPIKES WERE REMOVED
C
ISN 0091      IF(ISPIK.EQ.0) GO TO 675
ISN 0093      IF(ISPIK.EQ.1) ICNT=ICNT1
ISN 0095      IF(ISPIK.EQ.2) ICNT=ICNT2
ISN 0097      IF(ISPIK.EQ.3) ICNT=ICNT3
ISN 0099      IF(ICNT.EQ.0) GO TO 675
ISN 0101      DO 650 I=1,ICNT
ISN 0102      I1=ICNT-I+1
ISN 0103      IF(ISPIK.EQ.1) W=(SPIKL(I1)-1)*XSCAL
ISN 0105      IF(ISPIK.EQ.2) W=(SPIK2(I1)-1)*XSCAL
ISN 0107      IF(ISPIK.EQ.3) W=(SPIK3(I1)-1)*XSCAL
ISN 0109      W=W+XOFF
ISN 0110      YWHITE=HITE+YOFF
ISN 0111      CALL SYMBOL(W,YWHITE,H1,I1,0..-1)
ISN 0112      650  CONTINUE
ISN 0113      651  CONTINUE

C
C      PLOT HEADER INFO
C
ISN 0114      675  CONTINUE

```

```

ISN 0115      IF(IEAD(2).EQ.0) GO TO 725
ISN 0117      XL=1.5
ISN 0118      YL=0.07
ISN 0119      IF(IEAD(2).EQ.22) GO TO 700
ISN 0121      IF(IEAD(2).EQ.25) GO TO 701
ISN 0123      IF(IEAD(2).EQ.24) GO TO 702
ISN 0125      IF(IEAD(2).EQ.1) GO TO 703
ISN 0127      IF(IEAD(2).EQ.23) GO TO 704
ISN 0129      IF(IEAD(2).EQ.2) GO TO 705
ISN 0131      IF(IEAD(2).EQ.4) GO TO 706
ISN 0133      PRINT 699,IEAD(2)
ISN 0134      699  FORMAT(1X,'STATION I.D. NO. IS: ',15)
ISN 0135      GO TO 725
ISN 0136      700  CALL SYMBOL(XL,YL,H2,'ST: (22) KIP.',0.,13)
ISN 0137      GO TO 725
ISN 0138      701  CALL SYMBOL(XL,YL,H2,'ST: (25) MAT.',0.,13)
ISN 0139      GO TO 725
ISN 0140      702  CALL SYMBOL(XL,YL,H2,'ST: (24) ZLP.',0.,13)
ISN 0141      GO TO 725
ISN 0142      703  CALL SYMBOL(XL,YL,H2,'ST: (01) CTA.',0.,13)
ISN 0143      GO TO 725
ISN 0144      704  CALL SYMBOL(XL,YL,H2,'ST: (23) ALQ.',0.,13)
ISN 0145      GO TO 725
ISN 0146      705  CALL SYMBOL(XL,YL,H2,'ST: (02) CHG.',0.,13)
ISN 0147      GO TO 725
ISN 0148      706  CALL SYMBOL(XL,YL,H2,'ST: (04) TLD.',0.,13)
ISN 0149      725  XL=XL+14.*WTH
ISN 0150      CALL SYMBOL(XL,YL,H2,'CH:',0.,3)
ISN 0151      XL=XL+3.*WTH
ISN 0152      CALL SYMBOL(XL,YL,H2,KKL,0.,2)
ISN 0153      IF(IEAD(3).EQ.0) GO TO 742
ISN 0155      XIN=IEAD(3)
ISN 0156      POS=XL+4.*WTH
ISN 0157      CALL NUMBER(PDS,YL,H2,XIN,0.,-1)
ISN 0158      CALL WHERE(RETX,RETY,RETFAC)
ISN 0159      POS=RETX
ISN 0160      XIN=-IEAD(4)
ISN 0161      CALL NUMBER(POS,YL,H2,XIN,0.,-1)
ISN 0162      CALL WHERE(RETX,RETY,RETFAC)
ISN 0163      POS=RETX+2.*WTH
ISN 0164      XIN=IEAD(5)
ISN 0165      CALL NUMBER(POS,YL,H2,XIN,0.,-1)
ISN 0166      CALL WHERE(RETX,RETY,RETFAC)
ISN 0167      POS=RETX
C
ISN 0168      IF(IEAD(6).NE.0) GO TO 735
ISN 0170      CALL SYMBOL(POS,YL,H2,1IHR,0.,4)
ISN 0171      POS=POS+3.*WTH
ISN 0172      GO TO 738
C
ISN 0173      735  CALL SYMBOL(POS,YL,H2,122,0.,-1)
ISN 0174      CALL WHERE(RETX,RETY,RETFAC)
ISN 0175      POS=RETX
ISN 0176      XIN=IEAD(6)
ISN 0177      IF(XIN.GT.9.) GO TO 736
ISN 0179      CALL NUMBER(POS,YL,H2,ZERC,0.,-1)
ISN 0180      CALL WHERE(RETX,RETY,RETFAC)
ISN 0181      POS=RETX
ISN 0182      736  CALL NUMBER(POS,YL,H2,XIN,0.,-1)
ISN 0183      CALL WHERE(RETX,RETY,RETFAC)
ISN 0184      POS=RETX
C
ISN 0185      738  IF(HEAD(7).NE.0.) GO TO 740
ISN 0187      CALL SYMBOL(POS,YL,H2,1IHR,0.,4)
ISN 0188      GO TO 742
C
ISN 0189      740  CALL SYMBOL(POS,YL,H2,122,0.,-1)
ISN 0190      CALL WHERE(RETX,RETY,RETFAC)
ISN 0191      POS=RETX
ISN 0192      IIN=HEAD(7)
ISN 0193      IF((IN.GT.9) GO TO 741
ISN 0195      CALL NUMBER(PDS,YL,H2,ZERO,0.,-1)
ISN 0196      CALL WHERE(RETX,RETY,RETFAC)
ISN 0197      POS=RETX
ISN 0198      XIN=IIN
ISN 0199      CALL NUMBER(POS,YL,H2,XIN,0.,-1)
ISN 0200      ILAB=LAB+1
ISN 0201      GO TO(760,744,745,744),ILAB

```

```

C C          LABEL ROTATION INFO
C
ISN 0202      744 CALL WHERE(RETX,RETY,RETFAC)
ISN 0203      POS=RETX+2.*WTH
ISN 0204      CALL SYMBOL(POS,YL,H2,'ANGLE:',0.,6)
ISN 0205      XANG=ANG
ISN 0206      POS=POS+6.*WTH
ISN 0207      CALL NUMBER(POS,YL,H2,XANG,0.,1)
ISN 0208      CALL WHERE(RETX,RETY,RETFAC)
ISN 0209      POS=RETX+WTH
ISN 0210      CALL SYMBOL(POS,YL,H2,'DEG.',0.,4)

C
ISN 0211      POS=POS+5.*WTH
ISN 0212      CALL SYMBOL(POS,YL,H2,'GAIN FACTOR:',0.,12)
ISN 0213      POS=POS+12.*WTH
ISN 0214      XGAIN=GAIN
ISN 0215      CALL NUMBER(POS,YL,H2,XGAIN,0.,4)
ISN 0216      CALL WHERE(RETX,RETY,RETFAC)
ISN 0217      POS=RETX
ISN 0218      CALL SYMBOL(POS,YL,H2,'X A3',0.,4)
ISN 0219      IF(ILAB.EQ.2) GO TO 750

C C          LABEL FILTER INFO
C
ISN 0221      745 CALL WHERE(RETX,RETY,RETFAC)
ISN 0222      POS=RETX+2.*WTH
ISN 0223      CALL SYMBOL(POS,YL,H2,FILAB,0.,8)
ISN 0224      CALL WHERE(RETX,RETY,RETFAC)
ISN 0225      Y2=RETY
ISN 0226      POS=RETX
ISN 0227      IF(SPER.EQ.9999.) GO TO 746
ISN 0229      CALL NUMBER(POS,Y2,H2,SPER,0.,-1)
ISN 0230      CALL WHERE(RETX,RETY,RETFAC)
ISN 0231      POS=RETX
ISN 0232      IF(XLPER.EQ.9999.) GO TO 747
ISN 0234      XLPER=-XLPER
ISN 0235      IF(SPER.EQ.9999.) XLPER=-XLPER
ISN 0237      CALL NUMBER(POS,Y2,H2,XLPER,0.,-1)
ISN 0238      CALL WHERE(RETX,RETY,RETFAC)
ISN 0239      POS=RETX
ISN 0240      CALL SYMBOL(POS,Y2,H2,'SEC',0.,3)

C C          PLOT AND LABEL Y-AXIS
C
ISN 0241      750 CONTINUE
ISN 0242      HYTE=YMIN+YSCAL
ISN 0243      YINCR=YMAX/5.
ISN 0244      NUMDEC=-1
ISN 0245      IF(YINCR.LT.5.) NUMDEC=2
ISN 0247      DO 800 J=1,6
ISN 0248      XK=J-1
ISN 0249      YYY=XK*YINCR*YSCAL+YOFF
ISN 0250      CALL PLOT(0.875,YYY,3)
ISN 0251      CALL PLOT(1.125,YYY,2)
ISN 0252      XYPOS=YYMIN+YINCR*XK
ISN 0253      CALL NUMBER(0.5,YYY,H1,XYPOS,0.,NUMDEC)
ISN 0254      CONTINUE
ISN 0255      YYMIN=YMIN+YOFF
ISN 0256      YWHITE=HITE+YOFF
ISN 0257      CALL PLOT(1.,YYMIN,3)
ISN 0258      CALL PLOT(1.,YWHITE,2)
ISN 0259      CALL PLOT(0.,YWHITE,-3)
ISN 0260      CALL PLOT(0.,0.,5)
ISN 0261      801 CONTINUE
ISN 0262      RETURN
ISN 0263      END

```

NAME--PRPLT1

TYPE--IO

SOURCE--A. LAZAREWICZ

PURPOSE -- Generates a plot of an array on the high-speed line printer.

DESCRIPTION--CALL PRPLT1 (X, LB, LE, LS)

X - array to be plotted (single precision, real)

LB - first point to be plotted

LE - last point to be plotted

LS - point increment (1 means plot every point, 2 means
plot every other point, and so on)

```

ISN 0002      SUBROUTINE PRPLT1(X,LB,LE,LS)
C           FORTRAN SUBROUTINE FOR PLOTTING AN ARRAY X
C           LB IS THE FIRST POINT OF ARRAY X TO BE PLOTTED
C           LE IS THE LAST POINT OF ARRAY X TO BE PLOTTED
C           LS IS THE SKIPPING FACTOR
C           ARRAY NMT CONTAINS THE FORMAT FOR WRITE STATEMENT NUMBER 20
C           ROUTINE BY MARK ODEGARD, UPDATED ON GRSDAT AUGUST 1973
C           WILL NOT PLOT IF ABS(MAX. AMPLITUDE) IS <= 1.E-60
C           REVISED BY: ANDY LAZAREWICZ, HAWAII INSTITUTE OF GEOPHYSICS
C           LATEST VERSION: 01 APRIL 1976
C
C           DIMENSION NMT(9),X(1)
C           DATA NMT/'(1H','.15',''2X,1','PE13','.6,'''','
C           +'''', ''')' //,NM7/'.000'/
C 100 FORMAT('POINT      MAGNITUDE      +....+....+....+....+....+
C           1..+....+....+....+....+....+....+....+....+....+
C           2.+')
C 101 FORMAT('      +....+....+....+....+....+....+....+....+
C           1..+....+....+....+....+....+....+....+....+....+
C           2.+')
C           XMAX=X(LB)
C           XMIN=X(LB)
C           DO 10 I= LB,LE,LS
C           XMAX = AMAX1(X(I),XMAX)
C 10 XMIN = AMIN1(X(I),XMIN)
C           XMAX=ABS(XMAX-XMIN)
C           IF ((XMAX.LE.+1.E-60).AND.(XMAX.GE.-1.E-60)) RETURN
C           PRINT 100
C           DO 20 I= LB,LE,LS
C           MN1=5+(X(I)-XMIN)*100./XMAX
C           MN1= MN1/10
C           MN2 = MN1/10
C           NMT(7) = NM7+66536+MN2+256*(MN1-10*MN2)+(MN-10*MN1)
C 20 WRITE(6,NMT) I,X(I)
C           PRINT 101
C           RETURN
C           END

```

NAME--READ

TYPE--IO

SOURCE--A. LAZAREWICZ

PURPOSE--Reads and interprets one record from 7-TRK data tape.

Fills six arrays with data and supplies header information.

Interprets error codes from KREAD.

DESCRIPTION--CALL READ (NREC, IPRT)

NREC - the number of the record to be read

IPRT - print code

0 - print nothing (except errors), fill arrays

1 - print one-line header, fill arrays

2 - print long header, fill arrays, print arrays

3 - print one-line header, do not fill arrays

4 - print nothing (except errors), do not fill arrays

COMMON/SMACK/ contains data from tape:

A1 - vertical velocity channel

A2 - NS vel. channel

A3 - EW vel. channel

B1 - vertical displacement channel

B2 - NS disp. channel

B3 - EW disp. channel

HEAD(10) - header information (see listing)

IREC - number of the last record that was read

NOTES--In general, the only time a main program calls READ directly is to skip part of a data tape where there is a long (several days) section of data missing. For example, consider a tape that contains the following sets of data in one file:

1975-323-00:00:00 to 1975-326-15:00:00 and

1975-340-12:00:00 to 1975-350-03:00:00

A call to FIND with ISTART as a time in the second set of data may result in an error. FIND reads the first record and uses that start time to calculate the record number that corresponds to ISTART. Because of the gap, the calculated record number could be larger than the number of records in the file and an error may result. The solution is to CALL READ (NREC, 4), where NREC is a record number in the second stretch of data but before the start of the data to be read from the tape. This merely advances the tape past the gap. A subsequent CALL FIND will work properly.

TSN 0002

SUBROUTINE READ(NREC,IPRT)

THIS IS A TAPE READING PROGRAM FOR THE RAYLEIGH WAVES PROJECT. SUMMARY OF TAPE: 7 TRACK, 6006 6-BIT BYTES, ONE FILE PER TAPE. PLEASE SEE DOCUMENTATION ON USE OF THE PROGRAM. AS SPECIFIC INTERACTION WITH THE CALLING PROGRAM IS REQUIRED. LATEST VERSION: 16 MAY 1974.
WRITTEN BY ANDY LAZAREWICZ, HIG-215 X-8143.

TSN 0003

INTEGER*2 CH,IM(3500),IN(111),ICNV(6),IPAR(1998),LAP(2),ERR(25)

TSN 0004

DIMENSION IEAD(10),IBUF(1998),IA1(555),IA2(555),IA3(555),

TSN 0005

(B1(111),IB2(111),IB3(111))

TSN 0006

COMMON//SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),B3(111),

TSN 0007

HEAD(10),IREC

TSN 0008

EQUIVALENCE(HEAD(1),IEAD(1)),(KAP,LAP(1)),(A1(1),IA1(1)),

TSN 0009

(A2(1),IA2(1)),(A3(1),IA3(1)),(B1(1),IB1(1)),(B2(1),IB2(1)),

TSN 0010

(B3(1),IB3(1)),(IM(1),ERR(1))

TSN 0011

FORMAT(15(200A2),3A2)

TSN 0012

FORMAT(' *** DATA PARITY ERROR AT ',Z2,' - ',I3,' ***')

TSN 0013

FORMAT(' NORMALIZED LISTING IN VOLTS FOR RECORD ',IA1,' STATION ',

' ,I2,' , DATE: ',I4,'-',I3,' , TIME: ',I2,'::',I2,'::',F4.1,' ',I1,'

' ,A CHANNELS, ',I1,' B CHANNELS, SAMPLE RATE = ',F3.1,'/')

FORMAT(I4,1X,15(2X,I6))

FORMAT(' RECORD ',I4,' HAS ',I4,' BYTES, SHOULD BE 6006. DATA SKIP ',P0,')

FORMAT(I4,1X,3(2X,I6))

FORMAT(' SEC',2X,5(4X,'A1',6X,'A2',6X,'A3',2X))

```

TSN 0014      8   FORMAT(' SEC*.2X,5(4X,*B1*.6X,*B2*.6X,*B3*.2X))
TSN 0015      9   FORMAT(' RECORD ',I4,' , STATION ',I2,' , DATE & TIME: ',I4,'-',I3,'-
                   .-,I2,':',I2,'.',F4.1,' , ('I1','.',I1,''), (A,B) CHANNELS, SMPLR
                   *ATE: ',F3.1)
TSN 0016     10  FORMAT(' END OF FILE, ',I4,' RECORDS, DESIRED RECORD WAS ',I4)
TSN 0017     12  FORMAT(' ***** READ ERROR IN RECORD ',I4,'; ',25A2,' , RECORD SKIPP
                   *ED *****')

C               CHOOSE AND READ DESIRED RECORD
C
TSN 0018     104  LREC=NREC-TREC
TSN 0019      IF (LREC.GT.0) GO TO 103
TSN 0021      CALL KRDCK(IM(3500),IBYTE)
TSN 0022      TREC=TREC-1
TSN 0023      GO TO 104
TSN 0024      103  DO 11 J=1,LREC
TSN 0025      IREC=IREC+1
TSN 0026      CALL KREAD(IM,IBYTE)
TSN 0027      IF (IBYTE.NE.-40000) GO TO 101
TSN 0029      MREC=IREC-1
TSN 0030      WRITE(6,10) MREC,NREC
TSN 0031      IREAD(1)=-10
TSN 0032      GO TO 200
TSN 0033      101  IF (IBYTE.NE.-50000) GO TO 102
TSN 0035      WRITE(6,12) IREC,ERR
TSN 0036      IF (IREC.EQ.NREC) GO TO 200
TSN 0038      GO TO 11
TSN 0039      102  IF (IBYTE.EQ.6006) GO TO 11
TSN 0041      WRITE(6,5) IREC,IBYTE
TSN 0042      IF (IPRT.EQ.2) IPRT=1
TSN 0044      11    CONTINUE
TSN 0045      DO 15 J=1,6
TSN 0046      K1=IM(J)/256
TSN 0047      K2=IM(J)-K1*256
TSN 0048      DO 16 J1=1,6
TSN 0049      L1=K2/2
TSN 0050      L2=L1*2
TSN 0051      J2=(J-1)*12+13-J1
TSN 0052      TN(J2)=K2-L2
TSN 0053      16    K2=L1
TSN 0054      DO 17 J1=1,6
TSN 0055      L1=K1/2
TSN 0056      L2=L1*2
TSN 0057      J2=(J-1)*12+7-J1
TSN 0058      TN(J2)=K1-L2
TSN 0059      17    K1=L1
TSN 0060      15    CONTINUE

C               INTERPRET HEADER AND FORM FIXED/FLOAT HEAD ARRAY
C               1:RELATIVE RECORD, 2:STATION ID, 3:YEAR, 4:JULIAN DAY, 5:HOUR,
C               6:MINUTES, 7:SECONDS, 8:NUMBER OF A CHANNELS, 9:NUMBER OF B
C               CHANNELS, 10:SAMPLE RATE.
C
TSN 0061      IHEAD(1)=IREC
TSN 0062      IHEAD(2)=10*(8*IN(3)+4*IN(4)+2*IN(5)+IN(6))+8*IN(9)+4*IN(10)+
                   2*IN(11)+IN(12)
TSN 0063      IHEAD(3)=1970.+8*IN(15)+4*IN(16)+2*IN(17)+IN(18)
TSN 0064      IHEAD(4)=100*(2*IN(19)+IN(20))+10*(8*IN(21)+4*IN(22)+2*IN(23)+
                   *IN(24))+8*IN(25)+4*IN(26)+2*IN(27)+IN(28)
TSN 0065      IHEAD(5)=10*(2*IN(31)+IN(32))+8*IN(33)+4*IN(34)+2*IN(35)+IN(36)
TSN 0066      IHEAD(6)=10*(4*IN(37)+2*IN(38)+IN(39))+8*IN(40)+4*IN(41)+2*IN(42)+
                   *IN(43)
TSN 0067      HEAD(7)=10*(4*IN(44)+2*IN(45)+IN(46))+8*IN(47)+4*IN(48)+2*IN(49)+
                   *IN(50)+0.1*(8*IN(51))+4*IN(52)+2*IN(53)+IN(54))
TSN 0068      IHEAD(8)=8*IN(57)+4*IN(58)+2*IN(59)+IN(60)
TSN 0069      IHEAD(9)=4*IN(64)+2*IN(65)+IN(66)
TSN 0070      HEAD(10)=0.5*IN(67)+IN(68)+2*IN(69)+4*IN(70)

C               PRINT HEADER IF IPRT=1,2 IN APPROPRIATE FORMAT
C
TSN 0071      IF (IPRT.EQ.0) GO TO 28
TSN 0073      IF (IPRT.EQ.2) GO TO 65
TSN 0075      IF (IPRT.EQ.4) GO TO 200
TSN 0077      WRITE(6,9) (IHEAD(J),J=1,6),HEAD(7),(IHEAD(J),J=8,9),HEAD(10)
TSN 0078      IF (IPRT.EQ.3) GO TO 200
TSN 0080      GO TO 28
TSN 0081      65    WRITE(6,3) (IHEAD(J),J=1,6),HEAD(7),(IHEAD(J),J=8,9),HEAD(10)

```

```

C
C      NOW READ DATA: CONVERT<111(5(A1,A2,A3),1(B1,B2,B3))> TO
C      SSSA1,SSSA2,SSSA3,111B1,111B2,111B3.
C      MAX. BINARY COUNTS IN ANY CHANNEL IS 36767.
C      STUFF SEQUENTIAL DIGITAL DATA TO IBUF. SEARCH FOR PARITY BIT AND
C      LOAD INTO ARRAY IPAR.
C
ISN 0082      28   IF (IBYTE.EQ.6006) GO TO 31
ISN 0084      30   DO 32 J=1,1998
ISN 0085      32   IBUF (J)=40000
ISN 0086      33   GO TO 33
ISN 0087      31   JCNT=1
ISN 0088      34   DO 26 J=6,3000,3
ISN 0089      35   DO 22 J1=1,3
ISN 0090      36   ICNV(J1*2-1)=IM(J+J1)/256
ISN 0091      37   IARG=IM(J+J1)
ISN 0092      38   ICNV(J1*2)=MOD(IARG,256)
ISN 0093      39   DO 24 J1=1,4,3
ISN 0094      40   IARG=ICNV(J1)
ISN 0095      41   IL=MOD(IARG,256)
ISN 0096      42   IR=ICNV(J1+2)/2
ISN 0097      43   KAP=IL*2048+ICNV(J1+1)*32+IR
ISN 0098      44   IBUF (JCNT)=LAP(2)
ISN 0099      45   ICHK=0
ISN 0100      46   DO 23 J2=1,16
ISN 0101      47   ICHK=ICHK+MOD(KAP,2)
ISN 0102      48   KAP=KAP/2
ISN 0103      49   IARG=ICNV(J1+2)
ISN 0104      50   ICHK=ICHK+MOD(IARG,2)
ISN 0105      51   IPAR(JCNT)=MOD(ICCHK,2)
ISN 0106      52   JCNT=JCNT+1
ISN 0107      53   CONTINUE
C
C      CORRECT AND LIST DATA PARITY ERRORS
C
ISN 0108      26   DO 29 J=1,1998
ISN 0109      27   IF (IPAR(J).EQ.1) GO TO 29
ISN 0111      28   J2=(J-1)/18+1
ISN 0112      29   J3=J-(J2-1)*18
ISN 0113      30   J4=(J3-1)/3+1
ISN 0114      31   J5=J3-(J4-1)*3
ISN 0115      32   IF (J3.GT.15) GO TO 13
ISN 0117      33   IF (J5.EQ.1) CH=161
ISN 0119      34   IF (J5.EQ.2) CH=162
ISN 0121      35   IF (J5.EQ.3) CH=163
ISN 0123      36   J7=(J2-1)*5+J4
ISN 0124      37   GO TO 14
ISN 0125      38   IF (J3.EQ.16) CH=177
ISN 0127      39   IF (J3.EQ.17) CH=178
ISN 0129      40   IF (J3.EQ.18) CH=179
ISN 0131      41   J7=J2*5
ISN 0132      42   WRITE(6,2) CH,J7
ISN 0133      43   IFOR=3
ISN 0134      44   IBAK=3
ISN 0135      45   IF (J4.EQ.5) IFOR=6
ISN 0137      46   IF (J4.EQ.6) IFOR=18
ISN 0139      47   IF (J4.EQ.1) IBAK=6
ISN 0141      48   IF (J4.EQ.6) IBAK=18
ISN 0143      49   JL=J-IBAK
ISN 0144      50   JH=J+IFOR
ISN 0145      51   IF (JL.LT.1) JL=JH
ISN 0147      52   IF (JH.GT.1998) JH=JL
ISN 0149      53   IBUF(J)=(IBUF(JL)+IBUF(JH))/2
ISN 0150      54   CONTINUE
ISN 0151      55   CONTINUE
C
C      REASSIGN IBUF TO CHANNELS A & B
C
ISN 0152      29   JA=0
ISN 0153      30   JB=0
ISN 0154      31   JI=1
ISN 0155      32   DO 39 J=1,111
ISN 0156      33   DO 34 J1=1,5
ISN 0157      34   JA=JA+1
ISN 0158      35   A1(JA)=IBUF(JI)
ISN 0159      36   A2(JA)=IBUF(JI+1)
ISN 0160      37   A3(JA)=IBUF(JI+2)
ISN 0161      38   JT=JI+3
ISN 0162      39   JB=JB+1

```

```

ISN 0163      B1(JB)=IBUF(JI)
ISN 0164      B2(JB)=IBUF(JI+1)
ISN 0165      B3(JB)=IBUF(JI+2)
ISN 0166      JI=JI+3
39

C             NOW PRINT ARRAY IF IPRT=2
C

ISN 0167      IF (IPRT.NE.2) GO TO 200
ISN 0169      DO 69 J=1,555
ISN 0170      IA1(J)=A1(J)
ISN 0171      IA2(J)=A2(J)
ISN 0172      IA3(J)=A3(J)
ISN 0173      IF (J.GT.111) GO TO 69
ISN 0175      IB1(J)=B1(J)
ISN 0176      IB2(J)=B2(J)
ISN 0177      IB3(J)=B3(J)
ISN 0178      CONTINUE
ISN 0179      WRITE(6,7)
ISN 0180      DO 60 L=1,111
ISN 0181      TN(L)=(L-1)*5
ISN 0182      LL=(L-1)*5+1
ISN 0183      LH=LL+4
ISN 0184      60   WRITE(6,4) (IN(L),((IA1(K),IA2(K),IA3(K)),K=LL,LH))
ISN 0185      WRITE(6,8)
ISN 0186      DO 61 L=1,21
ISN 0187      TN(L)=(L-1)*25
ISN 0188      LL=(L-1)*5+1
ISN 0189      LH=LL+4
ISN 0190      61   WRITE(6,4) (IN(L),((IB1(K),IB2(K),IB3(K)),K=LL,LH))
ISN 0191      IN(22)=525
ISN 0192      WRITE(6,6) IN(22),(IB1(111),IB2(111),IB3(111))
ISN 0193      DO 75 J=1,555
ISN 0194      A1(J)=IA1(J)
ISN 0195      A2(J)=IA2(J)
ISN 0196      A3(J)=IA3(J)
ISN 0197      IF (J.GT.111) GO TO 75
ISN 0199      B1(J)=IB1(J)
ISN 0200      B2(J)=IB2(J)
ISN 0201      B3(J)=IB3(J)
ISN 0202      75   CONTINUE
ISN 0203      200  RETURN
ISN 0204      END

```

NAME--ROTATE
TYPE--DATA
SOURCE--D. CHESLEY

PURPOSE--Converts NS and EW data to radial and transverse data.

R is positive toward epicenter, T is positive to the left when viewing from station toward the epicenter.

DESCRIPTION--CALL ROTATE (PHI, G, NUM)

PHI - angle of rotation (N through E) in degrees

G - gain of channel A3 relative to A2

NUM - = 0 rotates data returned from FIND

= 1 rotates data returned from READ.

COMMON--/SEARCH/ contains data from FIND to be rotated if NUM = 0.

/SMACK/ contains data from READ to be rotated if NUM = 1

/TURN/ contains rotated data. CHR is radial; CHT is transverse

/ANGLE/ contains label information for PLT1

/X/ contains length of array to be rotated

ROTATE does not change any values in /SEARCH/, /SMACK/, or /X/.

PRECEDING PAGE BLANK-NOT FILMED

NAME--SEC2HD

TYPE--UTILITY

SOURCE--D. CHESLEY

PURPOSE-- converts seconds since 1968 (IGNORING LEAP YEARS and
1-sec adjustments of WWV(H)) to an array of year, day,
hour, minute, second.

DESCRIPTION--CALL SEC2HD (IB, IA)

IB - integer number of seconds since 1/1/68

IA - dimension = 5, integer array to contain year, day,
hour, minute, second.

NOTES--SEC2HD performs inverse process of HD2SEC.

```
TSN 0002      SUBROUTINE SEC2HD(IB,IA)
TSN 0003      DIMENSION IA(5)
TSN 0004      NUMSEC=365*24*3600
TSN 0005      IA(1)=IB/NUMSEC+1968
TSN 0006      IC=IB-(IA(1)-1968)*NUMSEC
TSN 0007      NUMSEC=24*3600
TSN 0008      IA(2)=IC/NUMSEC
TSN 0009      IC=IC-IA(2)*NUMSEC
TSN 0010      IA(3)=IC/3600
TSN 0011      IC=IC-IA(3)*3600
TSN 0012      IA(4)=IC/60
TSN 0013      IA(5)=IC-IA(4)*60
TSN 0014      RETURN
TSN 0015      END
```

NAME--SETCC, SETNP, SETXYN

TYPE--UTILITY

SOURCE--D. CHESLEY

PURPOSE--Initializes various parameters necessary for correct operation of entire system of subroutines. SETNP is used except in programs that generate a XNETICS plot or a CALCOMP plot. Those programs use SETXYN and SETCC, respectively.

DESCRIPTION--CALL SETCC, CALL SETNP, CALL SETXYN

SETCC, SETNP or SETXYN must be called once at the beginning of each main program

COMMON/SMACK/ contains IREC, which must be set to zero before any tape reading.

IREC counts records on the data tape /SMACK/ also contains the header array (HEAD(10)), which is initialized to zero

/FILT/ contains label information for PLT1

/PLTPAR/ contains variables used by PLT1

XOFF = x-distance in inches from initial pen position
to origin of plot (lower end of Y-axis)

YOFF = y-distance in inches from initial pen position
to origin of plot

H1 = height in inches of small letters in plot

H2 = height in inches of large letters in plot

PRECEDING PAGE BLANK-NOT FILMED

NOTES--The statement CALL SETCC must be used if the plot is to be made on a CALCOMP plotter. Care must then be taken that the total height of the plot to be generated (including YOFF) does not exceed 11 inches, but no other programming change need be made. The labels for the start time, station, and channel name might not be properly spaced in the CALCOMP plot.

```

ISN 0002      SUBROUTINE SETCC
ISN 0003      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),
               .B3(111),HEAD(10),IREC
ISN 0004      COMMON/FILT/FILAB(2),SPER,XLPER
ISN 0005      COMMON/PLTPAR/XOFF,YOFF,H1,H2
ISN 0006      DIMENSION IEAD(10),BUFFER(1000)
ISN 0007      EQUIVALENCE(HEAD(1),IEAD(1))
ISN 0008      SPER=9999.
ISN 0009      XLPER=9999.
ISN 0010      IREC=0
ISN 0011      H1=2./25.4
ISN 0012      H2=0.15
ISN 0013      XOFF=1.
ISN 0014      YOFF=0.25
ISN 0015      NBUF=4000
ISN 0016      CALL PLOTS(BUFFER,NBUF)
ISN 0017      DO 25 J=1,10
ISN 0018      IF((J.EQ.7).OR.(J.EQ.10)) GO TO 24
ISN 0019      IEAD(J)=0
ISN 0020      GO TO 25
ISN 0021
ISN 0022      HEAD(J)=0.
ISN 0023      24      CONTINUE
ISN 0024      RETURN
ISN 0025      END

```

```

ISN 0002      SUBROUTINE SETNP
ISN 0003      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),
               .B3(111),HEAD(10),IREC
ISN 0004      DIMENSION IEAD(10)
ISN 0005      EQUIVALENCE (HEAD(1),IEAD(1))
ISN 0006      IREC=0
ISN 0007      DO 25 J=1,10
ISN 0008      IF((J.EQ.7).OR.(J.EQ.10)) GO TO 24
ISN 0009      IEAD(J)=0
ISN 0010      GO TO 25
ISN 0011      HEAD(J)=0.
ISN 0012      24      CONTINUE
ISN 0013      25      RETURN
ISN 0014      END
ISN 0015

```

```
ISN 0002      SUBROUTINE SETXYN
ISN 0003      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),B3(111),
ISN 0004      •HEAD(10),IREC
ISN 0005      COMMON/FILT/FILAB(2),SPER,XLPER
ISN 0006      COMMON/PLTPAR/XOFF,YOFF,H1,H2
ISN 0007      DIMENSION IEAD(10)
ISN 0008      EQUIVALENCE (HEAD(1),IEAD(1))
ISN 0009      SPER=9999.
ISN 0010      XLPER=9999.
ISN 0011      IREC=0
ISN 0012      H1=2.,25.4
ISN 0013      H2=0.15
ISN 0014      XOFF=1.
ISN 0015      YOFF=0.25
ISN 0016      IUNIT=1
ISN 0017      CALL PLOTS(ND,NE,IUNIT)
ISN 0018      DO 25 J=1,10
ISN 0019      IF((J.EQ.7).OR.(J.EQ.10)) GO TO 24
ISN 0020      IEAD(J)=0
ISN 0021      GO TO 25
ISN 0022      HEAD(J)=0.
ISN 0023      24  CONTINUE
ISN 0024      RETURN
ISN 0025      END
```

NAME--SHRINK

TYPE-- UTILITY

SOURCE--D. CHESLEY

PURPOSE--makes data returned from FIND correspond exactly to
desired start and stop times.

DESCRIPTION--CALL SHRINK (IBEG , IEND)

IBEG - (dimension = 5, integer) contains year, day, hour,
minute, and second of desired first data point

IEND - (dimension = 5, integer) contains time of last data
point

COMMON--/X/ - IXMAX is the length of the data in CH1, CH2, and
CH3. IXMAX is decreased by SHRINK.

/SEARCH/ - contains the data

/SMACK/ - contains HEAD(10), which gives the start time of
the data

HEAD(10) is changed by SHRINK

NOTES--READ is capable of reading and interpreting entire records
(555 sec). SHRINK takes the data in CH1, 2, and 3, which
must be a multiple of the record length, and deletes data
from beginning and end so that only the desired data are
in CH1, CH2 and 3. SHRINK operates on all three channels
simultaneously and is called at the end of FIND.

PRECEDING PAGE BLANK-NOT FILMED

```

ISN 0002      SUBROUTINE SHRINK (IEEG, IEND)
ISN 0003      COMMON/X/IXMAX
ISN 0004      COMMON/SEARCH/CH1(5550),CH2(5550),CH3(5550)
ISN 0005      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),B2(111),
              .B3(111),HEAD(10),IREC
ISN 0006      INTEGER BEG,END,START,STOP
ISN 0007      DIMENSION IEAD(10),IHEAD(5),KSTART(5),IBEG(1),IEND(1)
ISN 0008      EQUIVALENCE(HEAD(1),IEAD(1))

C               CALL HD2SEC(IEEG,EEG)
ISN 0009      CALL HD2SEC(IEND,END)
ISN 0010      CALL HDCONV(KSTART,1)
ISN 0011      CALL HD2SEC(KSTART,START)
ISN 0012      STOP=START+IXMAX-1
ISN 0013      KXMAX=END-BEG+1
ISN 0014      DO 20 J=1,KXMAX
ISN 0015      J1=BEG-START+J
ISN 0016      CH1(J)=CH1(J1)
ISN 0017      CH2(J)=CH2(J1)
ISN 0018      CH3(J)=CH3(J1)
ISN 0019      CONTINUE
ISN 0020      20
C               CALL HDCONV(IEEG,-1)
ISN 0021      IXMAX=KXMAX
ISN 0022      RETURN
ISN 0023      END
ISN 0024

```

NAME--TABLE

TYPE--IO

SOURCE--D. CHESLEY

PURPOSE--Prints the output from CORRL8 in a simplified tabular form.

DESCRIPTION--CALL TABLE

COMMON--/PRINT/ contains data to be printed for each channel.

(1) (see below) is calculated from JMAX(I) and JMIN(I)
/COR/ - contains sum trace and necessary start and stop times
/X/ - contains length of sum trace in data points

NOTES-- TABLE prints correlation output for each channel, which includes:

- (1) start and stop times for reference and scan,
- (2) times of maximum and minimum correlation coefficient,
- (3) values of maximum and minimum correlation coefficient,
- (4) slopes at maximum and minimum of correlation (relative amplitude of scan with respect to reference),
- (5) standard error in slopes,
- (6) amplitude of scan signal in digital units (= slope x peak-to-peak amplitude of reference),
- (7) standard error of (6).

For the sum trace only (1), (2), and (3) are printed.

```

1SN 0002      SUBROUTINE TABLE
1SN 0003      COMMON/PRINT/JMAX(4),JMIN(4),CMAX(4),CMIN(4),SLOPE1(4),
               •SLOPE2(4),ERROR1(4),ERROR2(4),AMPL1(4),AMPL2(4),AMPER1(4),
               •AMPER2(4)
1SN 0004      COMMON/COR/SUM(2700),IREF1(5),IREF2(5),IORIG(5),
               •ISCAN1(5),ISCAN2(5)
1SN 0005      COMMON/X/TXMAX
1SN 0006      DIMENSION ANAME(4)
1SN 0007      INTEGER HEAD
1SN 0008      DIMENSION HEAD(5),ITIME(5)
1SN 0009      DATA ANAME/'CH 1'/'CH 2'/'CH 3'/'SUM'/
1SN 0010      CALL HODINV(ITIME,1)
1SN 0011      CALL HODSEC(ITIME,IT)
1SN 0012      CALL MAXMIN(SUM,TXMAX,CMAX(4),MAX,CMIN(4),MIN)
1SN 0013      JMAX(4)=MAX+IT-1
1SN 0014      JMIN(4)=MIN+IT-1

C
1SN 0015      PRINT 49
1SN 0016      FORMAT(1H1)
1SN 0017      PRINT 20,(IREF1(K),K=1,5),(IREF2(K),K=2,5),(ISCAN1(K),K=1,5),
               •(ISCAN2(K),K=2,5)
1SN 0018      20  FORMAT(1X,'REF FROM ',I4,'-',I3,'-',2(I2,:'),I2,2X,'TO ',
               •I3,'-',2(I2,:'),I2,4X,'SCAN FROM ',I4,'-',I3,'-',
               •2(I2,:'),I2,2X,'TO ',I3,'-',2(I2,:'),I2,2X)
1SN 0019      PRINT 9
1SN 0020      FORMAT(1X,//,22X,*****//)
1SN 0021      PRINT 10
1SN 0022      10  FORMAT(1X,'CHANNEL',10X,'TIME',8X,'CORR COEF',5X,'SLOPE',
               •4X,'LOG SLOPE',5X,'ERROR',9X,'AMPLITUDE',3X,'AMP ERROR')
1SN 0023      PRINT 11
1SN 0024      FORMAT(1X,//,20X,'DATA FOR MAXIMUM',/)

C
1SN 0025      DO 100 J=1,3
1SN 0026      CALL SEC2HD(JMAX(J),HEAD)
1SN 0027      IF(SLOPE1(J).EQ.0.) SLOPE=0.
1SN 0028      IF(SLOPE1(J).NE.0.) SLOPE= ALOG10(ABS(SLOPE1(J)))
1SN 0029      PRINT 12,ANAME(J),(HEAD(K),K=1,5),CMAX(J),
               •SLOPE1(J),SLOPE,ERROR1(J),AMPL1(J),AMPER1(J)
1SN 0030      12  FORMAT(1X,A4,6X,I4,'-',I3,'-',2(I2,:'),I2,3X,F7.4,3X,F11.6,
               •2X,F8.5,3X,F9.6,4X,F11.2,3X,F9.2,2X)

C
1SN 0031      100 CONTINUE
1SN 0032      CALL SEC2HD(JMIN(J),HEAD)
1SN 0033      PRINT 14,ANAME(4),(HEAD(K),K=1,5),CMIN(4)
1SN 0034      14  FORMAT(1X,A4,6X,I4,'-',I3,'-',2(I2,:'),I2,3X,F7.4,3X,F11(+''),
               •2X,B('+''),3X,9('+''),4X,F11('+''),3X,9('+''),/)

C
1SN 0035      PRINT 13
1SN 0036      FORMAT(1X,//,20X,'DATA FOR MINIMUM',/)

C
1SN 0037      DO 200 J=1,3
1SN 0038      CALL SEC2HD(JMIN(J),HEAD)
1SN 0039      IF(SLOPE2(J).EQ.0.) SLOPE=0.
1SN 0040      IF(SLOPE2(J).NE.0.) SLOPE= ALOG10(ABS(SLOPE2(J)))
1SN 0041      PRINT 14,ANAME(J),(HEAD(K),K=1,5),CMIN(J),SLOPE2(J),
               •SLOPE,ERROR2(J),AMPL2(J),AMPER2(J)
1SN 0042      200 CONTINUE
1SN 0043      CALL SEC2HD(JMIN(4),HEAD)
1SN 0044      PRINT 14,ANAME(4),(HEAD(K),K=1,5),CMIN(4)

C
1SN 0045      PRINT 9
1SN 0046      RETURN
1SN 0047
1SN 0048
1SN 0049
1SN 0050
1SN 0051

```

NAME--WRTSUM

TYPE--IO

SOURCE--D. CHESLEY

PURPOSE--writes the sum trace of one station permanently on disk
after several component correlations have been performed.

This trace is used for beam focusing.

DESCRIPTION-CALL WRTSUM (IF)

IF - Device or file name in JCL that describes the output
file.

COMMON--/SMACK/ contains the start time and station number

/X/ contains the length of the sum trace

/COR/ contains the sum trace

NOTES: User must supply the appropriate JCL with the main
program. Refer to sample program CORR for details.

```

ISN 0002      SUBROUTINE WRTSUM(IF)
ISN 0003      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),
ISN 0004      .B2(111),B3(111),HEAD(10),IREC
ISN 0005      COMMON/X/IXMAX
ISN 0006      COMMON/COR/SUM(2700),IREF1(5),IREF2(5),IORIG(5),ISCAN1(5),
ISN 0007      .ISCAN2(5)
ISN 0008      DIMENSION IT1(5),IEAD(10)
ISN 0009      EQUIVALENCE (HEAD(1),IEAD(1))
ISN 0010      CALL HDCONV(IT1,1)
ISN 0011      CALL HD2SEC(IT1,IT)
ISN 0012      WRITE(IF) IT,IXMAX,IEAD(2),SUM
ISN 0013      ENDFILE IF
                  RETURN
                  END

```

SAMPLE PROGRAMS AND JCL

The final section of this report presents three sample programs to show how the subroutines are used. The FORTRAN is simple and will not be discussed. Here we will try only to point out some important JCL considerations.

The first program (QUAKE) shows how the user reads data from the tape, plots the data, and rotates, filters, and plots the results. Note the order of the PLT1 call statements. The final CALL PLOT statement is necessary for all programs that create an output tape for the XYNETICS plotter. The first data set (B.B2823.BERG2823) contains the subroutines described in this report; the second contains the plotting routines that run the XYNETICS plotter (contact KARL HINCK, HIG, for details). The INTAPE DD statement describes the input tape with the data. Any name may be substituted for 'INPUT' but the remainder of the statement must remain as printed. The PLOTTAPE DD statement describes the output tape. X10740 and the file number are the only characters that may be changed. The file number must be 2 or larger.

```
//QUAKE JOB (2823,90S,250KR,3KI),CHESLEY
// EXEC FORTCLG,REGION,GO=250K
//SYSIN DD *
      COMMON/SEARCH/CH1(5550),CH2(5550),CH3(5550)
      COMMON/TURN/CHR(5550),CHT(5550)
      DIMENSION ISTART(5),ISTOP(5)
      DATA ISTART/1973,276,10,40,00/,ISTOP/1973,276,11,15,00/
      CALL SETXYN
      SCALE=1.5
      HYT=1.97
      N1=200
      BPFREQ=1./20.
      CALL LPFILT(W,N1,1.,BPFREQ)
      CALL HAMING(W,N1)
      CALL FLTADJ(N1,ISTART,ISTOP)
      CALL FIND(ISTART,ISTOP)
      CALL DSPYK(0)
      ILAB=0
      CALL PLT1(CH3,SCALE,HYT,0.,0.,'A3',0,ILAB)
      CALL PLT1(CH2,SCALE,HYT,0.,0.,'A2',0,ILAB)
      CALL PLT1(CH1,SCALE,HYT,0.,0.,'A1',0,ILAB)
      PHI=37.2
      GA=1.1210
      CALL ROTATE(PHI,GA,0)
      CALL DOFILT(CTH,W,N1,0)
      CALL DOFILT(CHR,W,N1,0)
      CALL DOFILT(CH1,W,N1,1)
      ILAB=3
      CALL PLT1(CTH,SCALE,HYT,0.,0.,'AT',0,ILAB)
      CALL PLT1(CHR,SCALE,HYT,0.,0.,'AR',0,ILAB)
      ILAB=2
      CALL PLT1(CH1,SCALE,HYT,0.,0.,'A1',0,ILAB)
      CALL PLOT(0.,HYT,999)
      STOP
      END
//LOAD.SYSLIB DD DSN=8.B2823.BERG2B23,DISP=SHR
//          UD DSN=T225660.XYNLIB,LOAD,DISP=SHR
//          DD DSN=SYS1.FORTLIB,DISP=SHR
//GO.INTAPE DD VOL=SER=INPUT,UNIT=7TRK,DISP=OLD,LABEL=(,NL),
//          DCB=(BLKSIZE=7000,RECFM=U,DEN=1)
//GO.PLOTTAPE DD UNIT=(DTRK,,DEFER),VOL=SER=X10740,DISP=OLD,
//          LABEL=(15,NL),DCB=DEN=2
//GO.SYSIN DD *
//
```

CORR shows how a correlation is accomplished. In this case a high-pass (in frequency) filter with 401 data points and a cutoff at 45 sec is applied to the data inside COREAD. A rotation is done inside COREAD (THETA and G are non-zero). Two channels are correlated and the sum trace is written in a permanent file.

The BLOCK DATA subprogram contains the times required by COREAD for tape reading. FT11, FT12, and FT13 describe the scratch files where COREAD places the tape data. These files are destroyed at the terminus of the job. FT15 describes the permanent file, which contains the sum trace for later beam focusing. If the program terminates abnormally, step B eliminates this file from the disk and catalog.

```

//CORR JOB (2823,295KR,3KI,200S),CHESLEY
// EXEC FORTCLG,REGION,LOAD=110K,REGION,GO=295K
//SYSIN DD *
      COMMON/COR/SUM(2700),IREF1(5),IREF2(5),I0RIG(5),
      .ISCAN1(5),ISCAN2(5)
      COMMON/ARRAY/N,W(1000)
      CALL SETXYN
      SCALE=1.5
      HYT=1.97
      HPFREQ=1./50.
      N=200
      THETA=24.5
      G=1.
      CALL HPFILT(W,N,1.,HPFREQ)
      CALL HAMING(W,N)
      IL=1
      CALL COREAD(IL,THETA+G)
      LAB=3
      NUMCH=2
      NFILE=15
      CALL CORRL8(2,SCALE,HYT,LAB,NUMCH,NFILE)
      CALL CORRL8(1,SCALE,HYT,LAB,NUMCH,NFILE)
      CALL TABLE
C
      CALL PLT1(SUM,SCALE,HYT,1..-1..,'SM',0,0)
      CALL PLOT(0.,HYT,999)
      STOP
      END
      BLOCK DATA
      COMMON/COR/SUM(2700),IREF1(5),IREF2(5),I0RIG(5),
      .ISCAN1(5),ISCAN2(5)
      DATA IREF1/1973.276.10.40.00/,IREF2/1973.276.10.54.00/
      DATA IDRIG/1973.276.10.25.00/
      DATA ISCAN1/1973.276.11.40.00/,ISCAN2/1973.276.12.10.00/
      END
//LOAD. SYSLIB DD DSN=B.B2823.BERG2823,DISP=SHR
//          DD DSN=T225660.XYNLIB,LOAD,DISP=SHR
//          DD DSN=SYS1.FORTLIB,DISP=SHR
//          DD DSN=SYS1.FORTSUB,DISP=SHR
//LOAD. SYSIN DD *
//GO.INTAPE DD VOL=SER=INPUT,UNIT=7TRK,DISP=OLD,LABEL=(7,NL),
//          DCB=(BLKSIZE=7000,RECFM=U,DEN=1)
//GO.PLOTTAPE DD VOL=SER=XI0740,UNIT=DTRK,DCB=DEN=2,DISP=OLD,
//          LABEL=(25,NL)
//FT11F001 DD UNIT=SYSDA,DCB=(RECFM=VS,LRECL=22204,BLKSIZE=7294,
//          BUFNO=1),SPACE=(TRK,(2,1))
//FT12F001 DD UNIT=SYSDA,DCB=(RECFM=VS,LRECL=22204,BLKSIZE=7294,
//          BUFNO=1),SPACE=(TRK,(2,1))
//FT13F001 DD UNIT=SYSDA,DCB=(RECFM=VS,LRECL=22204,BLKSIZE=7294,
//          BUFNO=1),SPACE=(TRK,(2,1))
//FT15F001 DD UNIT=USERDA,DISP=(,CATLG,DELETE),DSN=B.B2823.TLOC830,
//          DCB=(RECFM=VS,LRECL=22216,BLKSIZE=7294,BUFNO=1),SPACE=(TRK,(2,1))
//FT16F001 DD UNIT=USERDA,DISP=(,CATLG,DELETE),DSN=B.B2823.TLOC1830,
//          DCB=(RECFM=VS,LRECL=22216,BLKSIZE=7294,BUFNO=1),SPACE=(TRK,(2,1))
//GO.SYSIN DD *
//B EXEC PGM=IEHPROGM,COND=ONLY
//SYSPRINT DD SYSOUT=A
//SYSIN DD *
      UNCATLG DSNAME=B.B2823.TLOC830
      UNCATLG DSNAME=B.B2823.TLOC1830
//

```

SUMAVE shows how the permanent files created by several runnings of CORR may be added for a beam focusing effect. This program averages the part of each sum trace which is in common with the other sum traces, plotting the original and the averaged sum traces.

```

//SUMAVE JOB (2823,40S,295KR,3KI),CHESLEY
// EXEC FORTCLG,REGION=GO=295K
//SYSTIN DD *
      COMMON/X/IXMAX
      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),
      .B2(111),B3(111),HEAD(10),IREC
      DIMENSION IHEAD(10),XSUM(2700,10),IXC(10),ITIME(10),ASUM(2700),
      .IHEAD(5),JHEAD(5),ION(10),IOFF(10)
      EQUIVALENCE (HEAD(1),IFAD(1))
      CALL SETXYN
      IBEG=-1E+10
      IEND=-IBEG
      SCALE=1.5
      HYT=1.97
      IPLT=1
      NUMSUM=4
      IB=0
      IDEV=10+NUMSUM
      DO 100 I=11,IDEV
      IB=IB+1
      READ(I) ITIME(IB),IXC(IB),IEAD(2),ASUM
      IF(IPLT-1)180,50,80
      50   CALL SEC2HD(ITIME(IB),IHEAD)
      CALL HDCONV(IHEAD,-1)
      IXMAX=IXC(IB)
      CALL PLT1(ASUM,SCALE,HYT,1..-1.,'SM',0.0)
      80   J2=IXC(IB)
      DO 90 J=1,J2
      90   XSUM(J,IB)=ASUM(J)
      100  CONTINUE
C
C      CALCULATE START AND STOP TIMES
C
      DO 200 I=1,NUMSUM
      IBEG=MAX0(IBEG,ITIME(I))
      IS=ITIME(I)+IXC(I)-1
      IEND=MIN0(IEND,IS)
      200  CONTINUE
C
C      CALC. OFFSETS FOR EACH TRACE
C
      DO 300 I=1,NUMSUM
      ION(I)=IBEG-ITIME(I)+1
      IOFF(I)=IEND-IBEG+ION(I)
      300  CONTINUE
      DO 325 K=1,2700
      325  ASUM(K)=0.
C
C      AVERAGE THE SUMS
C
      DO 340 I=1,NUMSUM
      K=0
      J1=ION(I)
      J2=IOFF(I)
      341  CONTINUE
      DO 350 J=J1,J2
      K=K+1
      ASUM(K)=ASUM(K)+XSUM(J,I)
      350  CONTINUE

```

```

400  CONTINUE
DO 450 J=1,K
450  ASUM(J)=ASUM(J)/NUMSUM
C
C      PLOT THE AVERAGE
C
IXMAX=K
CALL SEC2HD(IBEG,IHEAD)
CALL HDCONV(IHEAD,-1)
IHEAD(2)=0
CALL PLTI(ASUM,SCALE,HYT,+1..-1..,'AV',0,0)
C
C      PRINT RESULTS
C
CALL MAXMIN(ASUM,IXMAX,SMAX,JMAX,SMIN,JMIN)
JMAX=JMAX+IBEG-1
JMIN=JMIN+IBEG-1
CALL SEC2HD(JMAX,IHEAD)
CALL SEC2HD(JMIN,JHEAD)
PRINT 402,(IHEAD(K),K=1.5),SMAX
PRINT 403,(JHEAD(K),K=1.5),SMIN
402 FORMAT(1X,'TIME OF MAX: ',I4,'-',I3.2X,I2,'::',I2,'::',I2,' MAX C'
.,'DEFF: ',F6.3,/)
403 FORMAT(1X,'TIME OF MIN: ',I4,'-',I3.2X,I2,'::',I2,'::',I2,' MIN C'
.,'DEFF: ',F6.3,/)
CALL PLOT(0.,HYT,999)
STOP
END
//LOAD.SYSLIB DD DSN=B.B2823.BERG2823,DISP=SHR
//          DD DSN=T225660.XYNLIB,LOAD,DISP=SHR
//          DD DSN=SYS1.FORTLIB,DISP=SHR
//          DD DSN=SYS1.FORTSUB,DISP=SHR
//LOAD.SYSIN DD *
//GO.PLOTTAPE DD VOL=SER=X51698,UNIT=DTRK,DCB=DEN=2,DISP=OLD,
// LABEL=(11,NL)
//FT11F001 DD DSN=B.B2823.KIPF,DISP=OLD
//FT12F001 DD DSN=B.B2823.MATF,DISP=OLD
//FT13F001 DD DSN=B.B2823.TLOFR,DISP=OLD
//FT14F001 DD DSN=B.B2823.CHGF,DISP=OLD
//GO.SYSIN DD *
//
```

FILTER1 illustrates the use of INFILT to retrieve the ground motion by deconvolving the instrument response from the tape data. This program calculates and plots a 'filter' for each channel. It reads the tape and applies these 'filters' and then plots the ground motion. Finally, FILTER1 filters the data with a high-pass filter and plots the results. The data set B.B2823.INRESP contains the Fourier coefficients of the instrument response for each of the three channels.

```

//FILTER1 JOB (2823,2805,295KR,4KI),CHESLEY
// EXEC FORTCLG,REGION,GO=295K
//SYSIN DD *
      COMMON/SMACK/A1(555),A2(555),A3(555),B1(111),
     .B2(111),B3(111),HEAD(10),IREC
      COMMON/SEARCH/CH1(5550),CH2(5550),CH3(5550)
      COMMON/X/IXMAX
      DIMENSION ISTART(5),ISTOP(5),W(1000)
      DIMENSION W1(513),W2(513),W3(513)
      DATA ISTART/1973,276,10,40,00/,ISTOP/1973,276,11,20,00/
      CALL SETXYN
      SCALE=1.5
      HYT=1.97
      N=256
      N1=400
      NSUM=N+N1
      CALL FLTADJ(NSUM,ISTART,ISTOP)
      HPFREQ=1./100.
      CALL HPFILT(W,N1,1.,HPFREQ)
      CALL HAMING(W,N1)
      ILAB=0
      IXMAX=513
      CALL INFILT(1,W1,N,1,14)
      CALL INFILT(2,W2,N,1,14)
      CALL INFILT(3,W3,N,1,14)
      CALL PLT1(W3,SCALE,HYT,0.,0.,'F3',0,ILAB)
      CALL PLT1(W2,SCALE,HYT,0.,0.,'F2',0,ILAB)
      CALL PLT1(W1,SCALE,HYT,0.,0.,'F1',0,ILAB)
      CALL FIND(ISTART,ISTOP)
      CALL DSPYK(0)
      CALL DOFILT(CH3,W3,N,0)
      CALL DOFILT(CH2,W2,N,0)
      CALL DOFILT(CH1,W1,N,0)
      CALL PLT1(CH3,SCALE,HYT,0.,0.,'G3',0,ILAB)
      CALL PLT1(CH2,SCALE,HYT,0.,0.,'G2',0,ILAB)
      CALL PLT1(CH1,SCALE,HYT,0.,0.,'G1',0,ILAB)
      CALL DOFILT(CH3,W,N1,0)
      CALL DOFILT(CH2,W,N1,0)
      CALL DOFILT(CH1,W,N1,1)
      CALL PLT1(CH3,SCALE,HYT,0.,0.,'G3',0,2)
      CALL PLT1(CH2,SCALE,HYT,0.,0.,'G2',0,2)
      CALL PLT1(CH1,SCALE,HYT,0.,0.,'G1',0,2)
      CALL PLOT(0.,HYT,999)
      STOP
      END
//LOAD.SYSLIB DD DSN=B.B2823.REPG2823,DISP=SHR
//          DD DSN=T225660.XYNLIB,LDAE,DISP=SHR
//          DD DSN=SYS1.FORTLIB,DISP=SHR
//          DD DSN=SYS1.FORTSUB,DISP=SHR
//LOAD.SYSIN DD *
//GO.INTAPE DD UNIT=7TRK,VOL=SER=X51045,DISP=OLD,
// DCB=(RECFM=U,BLKSIZE=7000,LEN=1),LABEL=(,NL)
//GO.PLOTTAPE DD VOL=SER=X51698,DISP=OLD,DCB=LEN=2,UNIT=DTRK,
// LABEL=(22,NL)
//GO.FT14F001 DD DSN=B.B2823.INRESP,DISP=SHR
//GO.SYSIN DD *
//
```